


AD-A114 343

CONTROL DATA CORP MONTEREY CA F/G 8/12
PROGRAM MAINTENANCE MANUAL POLAR ICE FORECAST SUBSYSTEM - ARCTIC--ETC(U)
OCT 81 P A HARR, T C PHAM, J P WELSH N00014-81-F-0028
NORDA-TN-122 NL

UNCLASSIFIED


1 of 2
47-3 Jan 82



Naval Ocean Research and
Development Activity
NSTL Station, Mississippi 39529



Program Maintenance Manual Polar Ice Forecast Subsystem - Arctic



DTIC FILE COPY

THIS DOCUMENT IS BEST QUALITY AVAILABLE.
THE COPY IS SUBJECT TO DUST AND CONTAINS A
SIGNIFICANT NUMBER OF PAGES WHICH DO NOT
REPRODUCE ACCURATELY.

P.A. Harr
T.C. Pham
Control Data Corporation
Monterey, California

DTIC
ELECTE
S MAY 13 1982 D
A

J.P. Welsh
Oceanography Division
Ocean Science and Technology Laboratory

October 1981

This document has been approved
for public release and sale; its
distribution is unlimited.

82 0.5-12 014

DISCLAIMER NOTICE

**THIS DOCUMENT IS BEST QUALITY
PRACTICABLE. THE COPY FURNISHED
TO DTIC CONTAINED A SIGNIFICANT
NUMBER OF PAGES WHICH DO NOT
REPRODUCE LEGIBLY.**

ABSTRACT

This manual provides a complete and detailed description of the dynamic thermodynamic sea ice model (PIFS-N), including all the necessary information for maintenance programmer personnel required to maintain the system.



Accession For	
DTIC GRA&I	<input checked="checked" type="checkbox"/>
DTIC TAB	<input type="checkbox"/>
Unannounced	<input type="checkbox"/>
Justification	
By	
Distribution/	
Availability Codes	
Dist	Avail and/or Special
A	

TABLE OF CONTENTS

Section 1	General Description	1
1.1	Purpose of the Maintenance Manual	1
1.2	Background	1
1.3	Terms and Abbreviations	3
Section 2	System Description	4
2.1	System Application	4
2.2	Security and Privacy	4
2.3	General Description	5
2.4	Program Description	8
2.4.1	Program ICEMDL	10
2.4.2	Input Model Subroutines	24
2.4.2.1	Subroutine MESH	24
2.4.2.2	Subroutine BNDRY	26
2.4.2.3	Subroutine OCEAN	28
2.4.2.4	Subroutine INITIAL	29
2.4.3	Processing Modules Subroutines	32
2.4.3.1	Subroutine XSUM	32
2.4.3.2	Subroutine FORM	32
2.4.3.3	Subroutine PLAST	34
2.4.3.4	Subroutine RELAX	36
2.4.3.5	Subroutine FELLIP	38
2.4.3.6	Subroutine FELLD1	39
2.4.3.7	Subroutine ADVECT	40
2.4.3.8	Subroutine DIFFUS	41
2.4.3.9	Subroutine HEAT	43
2.4.3.10	Subroutine BUDGET	47
2.4.3.11	Subroutine GROWTH	48
2.4.3.12	Subroutine ADJUST	50
2.4.3.13	Subroutine MEAN	51
2.4.4	Output Module Subroutines	52
2.4.4.1	Subroutine DIVERG	52
2.4.4.2	Subroutine UVPLOT	53

2.4.4.3	Subroutine BUOYD	54	
2.4.4.4	Subroutine HAPLOT	56	
2.4.4.5	Subroutine GROWDEC	57	
2.4.4.6	Subroutine PRNT	58	
3	Environment	59	
3.1	Equipment Environment	59	
3.2	Support Software	59	
3.3	Data Base	59	
3.3.1	General Characteristics	60	
3.3.2	Organization and Detailed Description	61	
Section 4	Program Maintenance Procedures	64	
4.1	Conventions	64	
4.2	Verification Procedure	64	
4.3	Error Conditions	64	
4.4	Special Maintenance Procedures	66	
4.5	Special Maintenance Programs	66	
4.6	Listings		
APPENDIX A	ICEMDL Flowcharts		
APPENDIX B	Grid Structure		
APPENDIX C	Listings		

SECTION 1 GENERAL DESCRIPTION

1.1 Purpose of the Program Maintenance Manual

The objective of this Program Maintenance Manual for the Dynamic Thermodynamic Sea Ice Model, PIFS-N, is to provide the maintenance programmer personnel with the information necessary to effectively maintain the system.

1.2 Background

Sea ice forecasting programs have been clearly connected with fleet polar operations since the early 1950's. When organizing and conducting the sea lift operations required for the establishment and resupply of arctic bases such as Thule, Greenland and the Distant Early Warning Line across Alaska and Canada, ice reconnaissance and forecasting services were requested.

Since the advent of the underice submarine operations in 1957, ice intelligence prediction services have been requested by submarine commands. Their operational forecast requirements deviated markedly from surface ship or icebreaker requirements. The submarine operator is primarily interested in knowing the distribution, in frequency and size, and depth of ice pressure ridges which may constitute a hazard to underice navigation particularly in shoal water.

The surface ship is primarily interested in knowledge of ice concentration, the distribution of the various stages of ice development and floe sizes.

Escalations of operational activities

in ice-covered waters over the past seven years with attendant navigation problems have focused Navy and national attention on the need for a more reliable sea ice forecasting program.

The recent establishment of the Navy NOAA Joint Ice Center is a strong indication that Navy and other governmental departments are moving forward to meet existing and full operational requirements.

In recent years, important contributions have been made to understand the dynamics of sea ice through the Arctic Ice Dynamics Joint Experiment (AIDJEX). Several mathematical models have been developed. A continuing effort is needed to evaluate the applicability of these models for sea ice forecasting.

The dynamic-thermodynamic Sea Ice Model was developed by the W. D. Hibler III (Hibler, 1979). The Naval Air Systems Command (NAIR-270G) tasked the Naval Ocean Research and Development Activity's Polar Oceanography Branch to implement the model utilizing the Fleet Numerical Oceanography Center (FNOC) environmental data base and Cyber 203.

The model uses atmospheric forecast and analysis data available at FNOC in the operational data base. The model outputs forecasts of ice drift, concentration, thickness, convergence/divergence plus ice and open water growth.

There have been a number of sea ice models appearing in the literature in the recent years. A list of applicable references to this model is presented below:

i) Hibler, W.D., 1980: Modeling a Variable Thickness Sea Ice Cover. Mon. Wea. Rev., 108, 1943-1973.

ii) Hibler, W.D. 1979: A dynamic sea Ice Model. J. Phys. Oceanogr., 9, 815-846.

iii) Pritchard, R.S., 1978: The effect of strength on simulation of sea ice dynamics. Proc. Fourth int. Conf. Port and Ocean Engineerin under Arctic conditions, D.E. Muggeridge, Ed., Memorial University of St. Johns, Newfoundland, 494-505.

iv) Pritchard, R.S., M.D. Coon and M.G. McPhee, 1977: Simulation of sea ice dynamics during AIDJEX. J. Prep. Vessel Tech., 99J, 491-497.

v) Thorndike, A.S., and R. Colony, 1980: Large-scale ice motion in the Beaufort Sea during AIDJEX, April 1975 - April 1976. Sea Ice Processes and Models, R.S. Prichard, Ed., University of Washington Press, 249-260.

vi) FNWC User Manual

vi) Computer Operational Manual.

1.3

Terms and Abbreviations

FNOC	Fleet Numerical Oceanography Center
NORDA	Naval Ocean Research and Development Activity
NPOC	Naval Polar Oceanography Center
NEDN	Naval Environmental Data Network

Section 2

SYSTEM DESCRIPTION

2.1

System Application

Fleet Numerical Oceanography Center is a large computer complex, tasked with the mission of providing worldwide environmental support to the U.S. fleets. To accomplish this mission, FNOC collects meteorological report data, analyzes the data and predicts changes in environmental conditions.

The Dynamic Thermodynamic Sea Ice model developed by Hibler is modified to use FNOC environmental data. The modified model gets input data from the FNOC data base. These data consist of wind data, surface pressure, surface vapor pressure, air specific humidity, air temperature, incoming and outgoing radiation on the FNOC 63 x 63 Northern Hemisphere grid (A01, A10, A11, A12, A16, A16, A20, A21), interpolates these data to the model grid to get initial boundary conditions.

The model computes ice drift, ice concentration, thickness, convergence/divergence rate plus thick and thin ice growth/decay rate.

2.2

Security and Privacy

The sea ice model does not currently have access to classified information nor does it produce classified output. Hence, security should be treated at appropriate levels, and the user is responsible for protection of any material used by the model.

The dynamic thermodynamic sea ice model has been modified to run on the Cyber 203 utilizing the FNOC environmental data base, FNOC library and plotting facility. In general, the modified model can be divided into three modules: -Input Module, Processing Module, Output Module.

Input module creates a model grid on the FNOC 63 x 63 Polar Stereographic grid, sets boundary and initial conditions for the model and obtains and interpolates input data to each model grid point.

The processing module can be divided into two parts which process two different mechanisms: the dynamic mechanism and the thermodynamic mechanism.

The heart of the dynamic part is subroutine RELAX which computes ice drift for the model.

The thermodynamic mechanism is processed by subroutine HEAT which estimates ice thickness, concentration and thick and thin ice growth/decay rate.

The output module calls many FNOC routines to format output data into CRANDIC format, and stores them for plotting and printing. A functional diagram of the model is shown in Figure 1. Figure 2 illustrates more detail of each functional division.

Figure 1

The functional diagram of the
Dynamic Thermodynamic Sea Ice Model





Figure 2

The chart of interrelationship of the major components of the system



2.4

Program Description

The following list of subroutine names and functions is provided for easy reference:

<u>NAME</u>	<u>FUNCTION</u>
PROGRAM ICEMDL	Main driving program for the model
Input Module	
SUBROUTINE MESH	Calculates FNOC (I, J) grid points for the model grid;
BNDRY	Sets up boundary masks;
OCEAN	Computes ocean surface currents;
INITIAL	Obtains initial atmospheric data.
Processing Module	
SUBROUTINE FORM	Sets up forces, drag coefficients, non-linear viscosities for use in each time step;
XSUM	Sums a vector;
PLAST	Calculates non-linear viscosities for plastic flow, used in FORM
UVDDFF	Converts U,V to direction and magnitude and vice versa
INTRP	Performs interpolation from the FNOC grid to the model grid;

RELAX	Solves linearized momentum balance with spatially varying bulk and shear viscosities. Uses sequential over-relaxation technique;
FELLIP	Calculates finite differences
FELLDI	for use in RELAX;
ADJUST	Estimates thickness and concentration at "open boundary" grid cells based on adjacent values;
MEAN	
ADVECT	Performs advection of ice
DIFFUS	thickness and concentration;
HEAT	Driving subroutine for thermodynamic calculations;
BUDGET	Computes thin and thick ice growth/decay rate;
AVG	Computes averaged input variables for staggered grid system;
GROWTH	Calculates changes in concentration and mean ice thickness due to growth and redistribution due to ridging.

Output Module

SUBROUTINE	DIVERG	Output convergence/divergence in CRANDIO format;
	UVPLOT	Outputs direction and magnitude of ice drift in CRANDIO format;
	HAPLOT	Outputs ice thickness and concentration in CRANDIO format
	PRNT	Provides hard copy print out of model variable arrays;
	STATPRT	Prints resource use statistics;
	GROWPEC	Outputs ice growth/decay rates in CRANDIO format.

2.4.1

Program ICEMDL

A brief description of the theory involved in this model is initially presented in order to help clarify and provide a reference for the subroutine descriptions subsequently presented.

The main driving program, ICEMDL, is designed to call the subroutines which set up the initial conditions, perform the equation integration and output the specified forecasts in CRANDIC format on the CDC CYBER 203 at FNOC.

The overall structure essentially consists of three main components:

- i) input and initial conditions;
- ii) equation integration;
- iii) output processing.

The initial conditions are determined from the atmospheric data available through the FNOC operational data base. A model grid is defined to cover the arctic ocean basin and is a subset of the FNOC hemispheric grid (Figure 1). The grid contains a square mesh with a distance of approximately 120 Km between grid points. Atmospheric variables are interpolated from the FNOC hemispheric grid to the model grid through the use of a 16 point Bessel interpolation scheme. The following atmospheric parameters are interpolated to the model grid;

- i) surface wind (u,v);
- ii) surface pressure;
- iii) surface vapor pressure;
- iv) surface air temperature;
- v) incoming solar radiation;
- vi) total heat flux at the surface;
- vii) sensible plus evaporative heat flux at the surface.

Input processing begins by determining the boundary masks to be used in the simulation. The boundary masks define the coastline configuration present within the model grid system. Further output processing involves the incorporation of the initial ocean currents and initial surface wind components. Other input variables listed above are obtained during the processing of the thermodynamic module which accesses the input module to obtain the needed atmospheric thermodynamic variables.

The overall structure of the processing model can also be considered to exist in the three main portions defined below. The first is a momentum balance which includes air and water stresses, coriolos force, internal ice stress and ocean tilt. Non-linear boundary layers for both the air-ice and ocean-ice surfaces are used. A key component is the force due to internal ice stress. This is defined by a constitutive law which relates the ice stress to the strain rate and ice strength. For this model a viscous-plastic constitutive law is followed.

The second feature of the processing module consists of continuity equations describing the evolution of the thickness characteristics on two levels. Two categories of ice thickness are assumed; thin ice (less than 0.5 m in thickness) and thick ice (greater than 0.5 m in thickness). To keep account of these categories two variables are maintained; ice thickness per unit area and the ice concentration which is defined as the fraction of area of a grid cell covered by thick ice. Thermodynamic terms are included on these continuity calculations.

The final component is an ice strength value which is taken to depend linearly upon the ice thickness and exponentially on the ice concentration.

The coupled non-linear equations are treated as an initial value problem using energy conserving finite differences. The momentum equations are integrated implicitly in order to avoid a time limit constraint. A relaxation technique is used on the set of simultaneous equations at each time step.

The numerical scheme uses a staggered grid which allows ice strength and ice velocities to vary in space. To a large degree this staggered grid is patterned after those used in primitive equation ocean models.

As mentioned above, initial conditions at all points and ice velocities at the boundaries are thereafter required to initiate the integration of the system of equations. The most natural condition is to take the ice velocity to be zero at the boundary. This can be accomplished at land boundaries or open ocean boundaries where there is no ice. This boundary condition does not affect the ice motion in such circumstances since, in the absence of ice the strength is zero. It is also possible to set an "open" boundary condition by setting the strength equal to zero near a boundary. This type of open boundary is used at the Spitzbergen-Greenland passage to form a natural inflow/outflow region (Figure 1).

In the computer code, three boundary masks are used to define the "closed" and "open" boundaries. Consequently by altering these masks, highly irregular boundaries may be taken into account.

Because of the strong ice interaction, the momentum equations are parabolic in form and hence have few numerical instability problems over longterm integrations. To avoid non-linear instabilities in longterm simulations which can arise from the non linear advection terms in the continuity equations, small

biharmonic and harmonic terms are added to the continuity equation.

A thermodynamic system is incorporated which specifies the ice growth rate as a function of thickness and time of year.

Input to ICEMDL

Input to the ICEMDL program exists on a number of files which must be set up before the actual model is run. Only a portion of these files are actually accessed by PROGRAM ICEMDL. The remainder of the input files is accessed by input module subroutines.

The input files are labeled as TAPE7=IN and TAPE8=DATE in the CY203 convention. TAPE8 contains the date time groups of the period for the model integration. The date time group (DTG) is the standard format defined at FNOC consisting of:

YYMMDDHH

where

YY = year;

MM = month;

DD = day;

HH = hour.

Each DTG is kept in one word and is valid for one day (time step). The DTG is used to access the proper fields from the CRANDIC data base consisting of the atmospheric data maintained by FNOC. Three DTG values are input to ICEMDL at each time step requiring new atmospheric data. The initial DTG values input for the very first time step are set up slightly differently than the other DTG values. For all accesses of the DTG file the

first DTG contains the DTG of the current day valid for that time step. The second DTG contains the DTG for 12 hours before the current day. For the initial group of DTG's the third position contains the DTG of the last time step of the previous run. This DTG is used to read the final fields produced by the previous run. These fields are used to restart the model simulation. Therefore, if a run was made to simulate the month of January (ending January 31, 1981) and a new run was to begin for February the initial line of the TAPE8 file would be;

81020100 81013112 81013100.

The DTG, 81020100, is the current DTG for the start of the simulation. The DTG 81013100 is the last day of the previous simulation and will be used to access the data for restarting the model. In reality input atmospheric data is entered into the model every 4 days (time steps). Therefore the DTG values, held in the model, change in increments of 4 days.

The file TAPE7 contains various types of input data used by the model. TAPE7 is accessed by ICEMDL to set the following variables;

NX, NY	-	dimension of the grid which holds the momentum variables;
NX1,NY1	-	dimension of the grid which holds the thermodynamic variables;
N3	-	number of points in the momentum variable grid;
N4	-	number of points in the thermodynamic variable grid.

ICEMDL Processing

The processing within ICEMDL begins by accessing the input files described in 2.4.1.1. The next processing involves the accessing of input module sub-routines. Subroutine MESH is the first input module routine which is accessed. This routine defines the model grid in terms of the FNOC hemispheric grid. MESH returns the i,j values of the model grid defined in terms of hemispheric grid.

Subroutine BNDRY is accessed after MESH. BNDRY returns the boundary masks to ICEMDL.

Subroutine OCEAN is called to formulate the u, v components of the surface ocean currents and returns them to ICEMDL.

At this point, some basic house keeping tasks are performed such as presetting several arrays to zero and accessing COPEN which is an FNOC routine which "opens" the CRANDIC file to be accessed by the model.

An error condition develops if the routine COPEN finds that it is unable to open the CRANDIC files. The program will terminate, stating that there is a COPEN ERROR on the STOP line of the dayfile.

Subroutine INITIAL is the final input module routine accessed by ICEMDL. Two calls are made to obtain the u and v atmospheric wind components respectively.

The next section of ICEMDL accesses the CRANDIC data base written by previous runs of the model. The variables; ice thickness, ice concentration and ice drift are read to restart the model simulation.

At this point all necessary information is available for the start of processing. The above described code is never executed again during the current run.

The actual equation integration starts with a series of calls to routines FORM and RELAX. FORM computes all parameters necessary for use in the relaxation scheme. These include the air and water drag coefficients, forces terms, ice strength terms, and the viscosity terms. Subroutine RELAX performs the relaxation technique.

There is a sequence of two calls to these routines. The first performs the prediction portion of the momentum time step. Before the first RELAX call, the third level of ice velocities and the centered ice velocities, held in UICEL, VICEC, are set equal to the level of ice velocities by Hibler (1980). During this procedure, the time step is halved. FORM is called in this first step to use the present ice velocity values to linearize the momentum equations.

The second calls of FORM and RELAX amount to the main forward time step of the "corrector" section of this "predictor-corrector" method. In this case the "predicted" values of the ice velocities are used in the second FORM call to estimate the viscosity parameters.

After the momentum equations have been implicitly stepped forward using the relaxation technique, several diagnostic calculations are carried out. The squared ice velocity and the squared ice velocity difference between the times, t and $t+1$ are computed. This is a simple measure of the change taking place in the ice velocity field during the time step advance.

The predicted ice velocity values are contained in the first level of the UICE and VICE arrays.

The ice velocity and divergence values are passed to the output module routines, UVPLLOT and

DIVERG respectively.

Following this momentum time step, the thermodynamic equations are explicitly stepped forward in time. Subroutine ADVECT is called to handle the dynamical portions of the continuity equations for ice thickness and concentration. Subroutine HEAT is called to obtain the thick and thin ice growth rates through the use of a heat budget. Subroutine GRCWTH is called to heat the thermodynamic portion of the continuity equations.

This concludes processing for the time integration. the remainder of the code is used to monitor diagnostic variables and the output modules.

Subroutine XSUM is used to obtain the total ice held within the grid, excluding outflow cells. The following diagnostic values are then computed;

- i) Total open water growth for each grid cell; HDIFF;
- ii) Net open water growth for the basin; GRSUM1;
- iii) Net ice growth for the basin; FHSUM;
- iv) Total ice in the outflow cells; TOUT.

The ice held in the outflow cells is explicitly determined through variables, THEFF and THEFF1. The variable THEFF1 contains the amount of ice in the open cells and is computed at the beginning of the time step.

The output module begins with a list of PRINT statements which form the hard copy output. Hard copy output is printed every four time steps. The

variable, LSTEP, is used to count time steps and branch to the output section on the fourth time step.

Subroutine PRNT is used to print the model arrays.

Subroutine ADJUST is called after the printed output is formulated. ADJUST is used to define the amount of ice held in the outflow cells for use at the beginning of the next time step.

Subroutine GROWDEC and HAPLOT are used in the output module to output the ice thickness, ice concentrations and growth/decay rates to the CRANDIO file maintained by the model.

The final function performed in ICEMDL is to decide if processing is complete. The variable ITSTEP which is input from TAPE8 defines the total number of time steps minus one to be used in the run. The variable ICOUNT is used to keep track of how many steps have currently been executed.

If more time steps are required, a check is made to determine whether new atmospheric wind data is needed. New wind data is used every four days. the variable, LSTEP, defines the fourth time step as described above. Subroutine INITIAL is called to access the CRANDIO file containing the wind data if needed. The program continues processing until time steps are no longer desired.

If the number of desired time steps has been completed, the diagnostic variables of;

- i) outflow;
- ii) net ice growth;
- iii) net open water growth;

are written to the file TAPE3 for use in a restart run if

desired. Subroutine STATPRT is called to print time use statistics on various routines used.

ICEMDL Output

The output of ICEMDL consists of forecasts of the following variables;

- i) ice thickness;
- ii) ice concentration;
- iii) ice drift;
- iv) ice divergence/convergence;
- v) ice strength;
- vi) ice growth.

These variables are output in printed form and also in CRANDIO files on the Cy203. CRANDIO is the type of file used operationally at FNOC, on the Cy203, for maintenance of the environmental data base. CRANDIO is analogous to ZRANDIO on the Cy170's and 6600's at FNOC.

The output CRANDIO files contain one record, produced every four time steps, for each of the above 6 variables. Specific information as to the format and structure of a CRANDIO file can be found in the appropriate FNOC technical write-up.

The records are labeled with the catalog name of each variable. The date of the record, and a tau value. The catalog names are defined as;

- i) FFF - ice speed;
- ii) DDD - ice direction;
- iii) THK - ice thickness;
- iv) CON - ice concentration;

- v) PRS - ice strength;
- vi) HDF - ice growth;
- vii) GAR - open water growth;
- viii) DIV - convergence/divergence.

Interfaces

Program ICEMDL interfaces with subroutines which comprise the input, processing and output modules. The following table defines all interfaces between these routines and ICEMDL. Specific arrays are defined under Tables and Items.

<u>Subroutine Name</u>		<u>Interfaces</u>
MESH	receives	- NX, NY, NX1, NY1 NUMBER - number of points in grid;
	returns	- GRDI - i grid points; GRDJ - j grid points;
BNDRY	receives	- NX, NY, NX1, NY1
	returns	HEFFM - thermodynamic variables boundary mask; UVM - momentum variables boundary mask; OUT - outflow boundary mask;
OCEAN	receives	- NX, NY, GRDI, GRDJ, UVM;
	returns	- GWATX - ocean current u components GWATY - ocean current v components;
COPEN	receives	- IFILE - CRANDIO file name
	returns	- ISTAT - status of file open attempt;

INITIAL	receives	- file unit number, NUMBER, GRDI, GRDJ, IDTG, DTG array, ITAU - tau value;
	returns	- variables read from FNOC data base;
CREADER	receives	- IFILE - array for data; LABEL - record name; catalog name; record length;
	returns	- read status, IS;
DDFFUN	receives	- DD, FF - direction and force of current or drift;
	returns	- U, V components;
XSUM	receives	- HEFF - ice thickness array NX1, NY1;
	returns	- total of array - THEFF or THEFF1;
PRNT	receives	- array name; dimensions of array; positions to be printed;
FORM	receives	- UICE, VICE, ETA, ZETA, AMASS, GAIRX, GAIRY, GWATX, GWATY, OUT, HEFFM, NX, NY, NX1, NY1, HEFF, AREA;
	returns	- DRAGS, DRAGA, DIV;
RELAX	receives	- UICE, VICE, ETA, ZETA, AMASS, GAIRX, GAIRY, GWATX, GWATY, DRAGS, DRAGA, OUT, HEFFM, NX, NY, NX1, NY1, HEFF, AREA;
	returns	- UICE, VICE;
DIVERG	receives	- DIV, NX, NY, GRDI, GRDJ, IDTG, ITAU;
UVPLOT	receives	- UICEC, VICEC, GRDI, GRDJ, NX, NY;

ADVECT	receives	- NICEC, VICEC, HEFF, DIFFI, LAD, HEFFM, NX, NY, NX1, NY1;
	returns	- HEFF or AREA, DIFFI;
HEAT	receives	- GRDI, GRDJ, HEFF, AREA, GAIRX, GAIRY, ITAU, IDTG, NX1, NY1, NUMBER;
	returns	- FC, FHEFF;
GROWTH	receives	- HEFF, AREA, HC, A22, FHEFF, FO, HCORR, HEFFM, OUT, NX1, NY1;
	returns	- HEFF, AREA, GAREA;
HAPLOT	receives	- HEFF, AREA, IDTG, ITAU, GRDI, GRDJ, NX, NY;
GRCWDEC	receives	- HDIFF, FHEFF, GAREA, IDTG, ITAU, NX1, NY1;
ADJUST	receives	- HEFF, AREA, OUT, HEFFM, NX, NY, NX1, NY1;
	returns	- HEFF, AREA.

ICEMDL Tables and Items

The following lists define all common blocks and major variable items used in ICEMDL.

I. Common Blocks

/BUOY/	BUOYI, BUOYJ	- Buoy position in terms of the FNOC I, J grid;
	BX, BY	- Buoy positions in terms of the model x, y grid;
/FORCE/	FORCEX	- x component of external force plus ice pressure gradient;
	FORCEY	- y component of external force plus ice pressure gradient;

/STEP/	DELTAT	- Time step in seconds;
	DELTAX,	- mesh size in meters, x, y
	DELTAY	directions respectively;
/PRESS/	IDENT	- CRANDIC record indentification block;
	DATA	- hemispheric atmospheric data;
	FILL	- filler to put the block on small page boundary (required by CRANDIC software);
/IJ/	IJ63	- I,J grid points of SKILES current data;
/DD/	ID	- CRANDIC identification block for ice drift direction;
	DD	- ice drift directions;
	FILLD	- filler for small page boundary;
/FF/	IF, FF,	- Same as /DD/ except for ice drift speeds;
	FILLF	
/AR/	IDA, ARRAY,	- Same as /DD/ except for ice concentration.
	FL	

Variable Items:

UICE	- u component of ice velocity
VICE	- v component of ice velocity
ETA	- non linear shear viscosity
ZETA	- non linear bulk viscosity
GAIRX	- u component of wind
GAIRY	- v componet of wind
AMASS	- ice mass per unit area
HEFF	- mean ice thickness per unit area
AREA	- fraction of area covered by thick ice
UICEC	- Intermediate ice velocities for
VICEC	- use in semi-implicit time step
GWATX	- u component of ocean currents
GWATY	- v component of ocean currents

STRESS	-	XX, YY and XY components of ice stress
FHEFF	-	growth rate of thick ice
FO	-	growth rate of thin ice
DRAGA	-	water drag plus Coriolos parameter
DRAGS	-	water drag plus inertial term
DIV	-	ice convergence/divergence

2.4.2 Input Module Subroutines

2.4.2.1 Subroutine MESH

Subroutine MESH is used to create the model grid. The grid is constructed as a subset of the FNOC hemispheric grid.

Input to MESH

Subroutine MESH receives input from 2 sources. The first source is the formal parameters from ICEMDL. MESH also reads the input file labeled TAPE7. The following variables are contained in the formal parameter list;

- i) GRDI, GRDJ - computed in MESH,
and contain the i,
j coordinates of the
model grid
- ii) NX, NY, NX1, NY1, N - grid sizes,
defined in TAPE 7.

The following variables are obtained from the input file TAPE7;

- i) I0, I1 - Defining i grid points on the FNOC hemispheric grid;
- ii) J0, J1 - Defining j grid points on the FNOC hemispheric grid;
- iii) N - The number of points in each row and column in the model grid.

Subroutine MESH creates a square grid. The variables I0, I1, J0, J1 are defined as follows;

x	x
i, j	I1, J1
x	x
I0, J0	i, j

Therefore I0, J0 define the bottom left corner of the desired model grid and I1, J1 define the upper right corner of the model grid. MESH fills in the remainder of the grid, depending upon N. All i, j coordinates are in reference to the hemispheric, 63 x 63 grid of FNOC.

Processing

The processing of subroutine MESH begins by reading all necessary input data from TAPE7. From the variable, N, the values of NX, NY and NX1, NY1 are computed. The actual grid is then formulated using the specified corner points and the number of points desired in each row (column). The column points are defined, stored in GRDJ, followed by the row points stored in GRDI.

After the entire grid is formed, the MESH size is computed utilizing the characteristics and map factor of the polar stereographic grid. The map factor of the model grid is also computed.

The final function of the routine is to compute the initial buoy positions in terms of the newly constructed model grid.

Output

Subroutine MESH produces printed output specifying the following;

- i) Corner grid points;
- ii) mesh size of model grid;
- iii) map factor;
- iv) buoy grid locations.

Interfaces

Subroutine MESH does not call any other subroutines.

Tables and Terms

All common blocks and major variables, used in MESH are defined under the ICEMDL section.

2.4.2.2

Subroutine BNDRY

Subroutine BNDRY is called to set up the boundary masks for the thermodynamic, momentum and outflow grids. A boundary mask consists of an array which

contains a 1 in grid locations where computations are performed and a 0 on all boundary points. By altering these masks one can obtain any desired boundary or coastline configuration.

Input

The respective boundary masks are read from the input file labeled TAPE7. The grid sizes are input through the formal parameter list interfaced with ICEMDL.

Processing

The standard FORTRAN READ function is used to access TAPE7 and move the boundary masks to the respective locations.

Output

The arrays, UVM, HEFFM and OUT are created by BNDRY.

Interfaces

Subroutine BNDRY does not call any other subroutines.

Tables and Items

The following major variables are used;

UVM - boundary mask for momentum
 variables;

HEFFM - boundary mask for
thermodynamic variables
OUT - boundary mask containing
outflow points.

2.4.2.3

Subroutine OCEAN

Subroutine OCEAN is used to define the surface ocean currents. These currents are defined by the SKILES sea ice drift model used at FNOC.

Input

Ocean current directions are read from the input file TAPE7. These direction values are on the model grid. The values were interpolated from the SKILES grid to the current grid and the results placed on TAPE7.

The model grid size and i, j coordinates of the model grid are passed to OCEAN from ICEMDL through the formal parameter list.

Processing

The ocean current magnitudes are located in the DATA statement defining the array WF. The ocean current magnitudes are input from TAPE7 through the use of a standard READ. The current magnitudes are converted from cm/sec to m/sec and placed into a model grid. The current directions, on TAPE7, also needed to be multiplied by 10. For example a direction of 270 is read in as 27.

The current directions and magnitudes are converted to u, v components with the FNOC routine

DFFFUV. Details pertaining to the function of this routine are contained in the standard FNOC subroutine write-ups. The code is placed within this program because the library is not available to the CY203 at the time of this writing.

Output

The arrays GWATX, GWATY are produced in OCEAN.

Interfaces

Subroutine OCEAN interfaces with subroutine DFFFUV which is a standard FNOC library routine used to convert a direction and magnitude to u, v components.

Tables and Items

All major variables contained in OCEAN are defined under ICEMDL.

2.4.2.4

Subroutine INITIAL

Subroutine INITIAL is used to access FNOC CRANDIC data on the CY203 and place the specified atmospheric data into the model grid.

Input

The main input to INITIAL is obtained from ICEMDL through the formal parameter list. The

variable, N0, specifies which field is to be accessed from the CRANDIO data base. Value of N0 specifies which position in array IRCD is to be used. IRCD holds the catalog names of the various atmospheric data input to the model. The array, IDTG, contains the data time group to be used in reading the data. ITAU is the tau value and N is the number of rows (columns) in the model grid. The arrays GRDI, GRDJ are defined as in MESH.

Processing

The first section of code in INITIAL is setting up the CRANDIO record name. This is a 2 word ASCII label. The first word contains the following;

- i) Catalog name of data;
- ii) flaps character;
- iii) length of record.

The second word contains the DTG. All of this information is masked together in array LABEL. The FNOC routine, CHECKNC, is used to determine whether the specified data is present on the CRANDIO file. If not present the program terminates with the following message;

STOP CHECKNC NO DATA INITIAL.

Providing the data is present, the FNOC routine CREADER is used to read the hemispheric data into array, DATA.

Subroutine INTRP is used to interpolate the hemispheric data to the model grid. INTRP is an FNOC subroutine which performs the interpolating function.

A detailed description of the operations of INTRP is available in the FNOC utility subroutine documentation.

Outputs

Subroutine INITIAL provides for a hard copy print of the requested record label. The array, GAIR, is used to store the resultant data placed in the model grid.

Interfaces

Subroutine INITIAL interfaces with the CRANDIO data base software at FNOC plus a utility library routine, INTRP. Detailed descriptions on all these routines are available as standard products of FNOC.

Tables and Items

The major variables, used in INITIAL, are defined in ICEMDL. The array IRCD is used to maintain the respective catalog names of the CRANDIO data. These catalog names are defined as follows;

- i) A20 - u wind components;
- ii) A21 - v wind components;
- iii) A10 - atmospheric temperature at the surface;
- iv) A01 - surface pressure;
- v) A12 - surface vapor pressure;
- vi) A11 - shortwave radiation;
- vii) A18 - total heat flux;
- viii) A16 - sensible plus evaporative heat flux.

2.4.3 Processing Module

2.4.3.1 Subroutine XSUM

All input to XSUM is provided by ICEMDL, through the parameter list.

Processing

Subroutine XSUM computes a simple sum of an array.

Output

The sum, contained in SI, is produced by XSUM.

Interfaces

No subroutines are called by XSUM.

Tables and Items

No new major variables are defined in XSUM.

2.4.3.2 Subroutine FORM

Subroutine FORM is used to calculate the drag coefficients, external forces and ice strength parameters for use in the time integration of the momentum equations.

Input

Subroutine FORM receives all required input from ICEMDL through the formal parameters. All of the variable definitions passed to FORM are presented under ICEMDL. Certain constants are defined as follows;

- i) FCOR - average coriolis parameter;
- ii) RHOAIR - air density;
- iii) SINWIN - sine of air turning angle;
- iv) COSWIN - cosine of air turning angle;
- v) SINWAT - sine of ocean turning angle;
- vi) COSWAT - cosine of ocean turning angle;
- vii) ECCEN - ratio of the axes of the plastic yield curve.

Processing

Subroutine FORM initially calculates the variables required to obtain the external forces operating upon the ice. Within the first major loop the ice mass per unit area, coriolis, non-linear water stress coefficient and antisymmetric water drag, DRAGA, are computed. The next major loop calculates the non-linear air stress and the symmetric water drag term, DRAGS. These terms are calculated in a separate loop due to a different grid requirements of the GAIRX, GAIRY (wind component) term (See Appendix A).

The remaining portion of the subroutine deals with finalizing the external force terms and accessing Subroutine PLAST to compute non-linear shear and bulk viscosities respectively. Before PLAST is called, the ice strength, PRESS, is computed. After PLAST is called the computed viscosities are set to zero at the outflow points by multiplying by the boundary mask OUT.

Finally, the external force components term is combined with the ice pressure gradient.

Output

The results of processing in routine FCRM are stored in DRAGS, DRAGA, FORCEX, FORCEY, ETA, ZETA, and PRESS. These variables are defined under ICEMDL.

Interfaces

Subroutine FCRM interfaces with routine PLAST. Subroutine PLAST calculates the non linear viscosities based on a Plastic yield curve.

Tables and Items

Subroutine FCRM operates upon a number of major variables which are defined under ICEMDL.

2.4.3.3

Subroutine PLAST

Subroutine PLAST is used by subroutine FORM to calculate the non linear viscosity terms based on a plastic yield curve.

Input

Subroutine PLAST receives all input parameters from FORM, through the formal parameter list.

Processing

The first main loop of PLAST uses the ice drift components to calculate the XX, XY, YY strain rates of the ice (E11, E12, E22 respectively). These components are used, with the constitutive law to calculate the non-linear bulk viscosity. The bulk viscosity is in turn used to compute the non-linear shear viscosity.

The final computation within PLAST is the calculation of the XX, XY, YY components of ice stress plus the divergence is calculated from the XX, YY strain rates.

Output

The main output of PLAST is contained in the arrays ETA, ZETA and sent to FORM through the parameter list.

Interfaces

Subroutine PLAST calls no other subroutines.

Tables and Items

The main variables of PLAST which have not been identified previously are;

- i) E11, E12, E22 - XX, XY, YY strain rates respectively.

2.4.3.4

Subroutine RELAX

Subroutine RELAX is the main routine of the processing module. This routine applies a relaxation technique to the dynamical equations for their numerical integration in time. Much numerical detail is contained in the routine and described by Hibler (1979).

Input

Subroutine RELAX receives all input from ICEMDL through the parameter list.

Processing

The processing of RELAX is broken into a number of separate modules. The first 3 major loops perform operations involving the previous time values of u , v plus the evaluation of the diagonal components of the computation matrix.

The main loop (103) performs the iterative relaxation scheme. This loop performs all necessary calculations to obtain a new estimate of the u , v ice drift components (UICE, VICE). After the new components are calculated, 2 checks are made. The first check examines the number of iterations completed to determine if more than 1300 have taken place. If so, the routine shall end printing a message stating more than 1300 iterations have occurred with no convergence. The second check searches for the 100th iteration. At this point the routine switches from a over relaxation scheme to a straight relaxation scheme.

After the checks have been executed, the difference between the new solution and previous

iterative solution is computed. If the difference lies within an accepted tolerance the routine ends. If the difference does not meet the tolerance specification another iteration is performed. The old iteration value is stored in the third level of arrays UICE, VICE while the new iterative solution is placed in the first level of arrays.

The relaxation code is made more complex by the separation of the finite difference computations into subroutines, FELLIP and FELLDL. The code is also generalized to fit into the predictor-corrector scheme previously defined. The parameter, THETA, defines whether backwards, centered, or forward time steps are used. A value of 0.5 initiates a centered time and a value of 0 dictates a forward step.

Outputs

A printed output message is made at the completion of the relaxation procedure. The message states the number of iterations used and the value of the difference between iterations at the end. The results of the processing are placed in UICE, VICE, level 1.

Interfaces

Subroutine RELAX interfaces with routines FELLIP and FELLDL. These routines calculate finite differences used in the relaxation routine.

Tables and Items

A large number of variables are used internally by RELAX. All major variables, however, are defined under the description of ICEMDL.

2.4.3.5

Subroutine FELLIP

Subroutine FELLIP is used to calculate finite differences used in the relaxation technique.

Input

All required input to FELLIP is provided in the parameter list and passed to FELLIP from RELAX.

Processing

Subroutine FELLIP operates on one grid position at a time. The position is defined by the input variable, i, j, k. FELLIP is called a number of times producing various terms needed by the relaxation routine at each call.

The code remains a very straight forward calculation of the finite difference approximations of the specified terms.

Output

The array, F, holds all resultant calculations.

Interfaces

No further subroutines are called by FELLIP.

Tables and Items

No new major variables are used in FELLIP.

2.4.3.6

Subroutine FELLD1

Subroutine FELLD1 is also used to calculate finite differences for the relaxation code.

Inputs

All required input to FELLD1 is supplied in the parameter list by RELAX.

Processing

Unlike FELLIP, FELLD1 operates upon the entire grid during one call. The level of the array to be altered is specified by input variable, K (e.g., 1, 2, or 3). The input variable, S1, defines the differencing constants.

Outputs

The output of FELLD1 is held within the array, F.

Interfaces

No subroutines are called by FELLD1.

Tables and Items

No new major variables are used in FELLD1.

2.4.3.7

Subroutine ADVECT

Subroutine ADVECT handles the dynamical portions of the thermodynamic continuity equations.

Input

Subroutine ADVECT receives all necessary input from ICEMDL through the formal parameter list. These variables are defined under ICEMDL and any functions performed by these variables are defined below.

Processing

Subroutine ADVECT performs the explicit time stepping procedure of the dynamical portions of the thermodynamic continuity equations. The routine is designed to operate in two separate finite difference schemes. The input variable, LAD, determines whether a backward Euler or Leapfrog scheme is followed. If LAD is 1.0 then the leapfrog scheme is followed, otherwise the Backward Euler is used.

Initially the ice thickness (HEFF) and ice concentrations (AREA) are stepped forward in time by transferring the grid point values to the next lower level. Therefore, the current values are moved to level 2 of the array while the new values are put into level 1. The subroutine is called twice by ICEMDL, one time processing HEFF and secondly processing AREA.

The finite difference approximation to the respective variable and a following check on the finite differencing scheme are the next major processing actions. If the Backward Euler scheme is used (LAD is 0) the scheme is continued to finish the necessary

computations required by this scheme.

After the computation is complete for both schemes, the subroutine DIFFUS is called to calculate a smoothing term which is used to comprise the final data value.

Output

The array HEFF, which is internal to ADVECT, holds the final calculations. These values are transferred to HEFF and AREA in ICEMDL.

Interfaces

Subroutine ADVECT utilizes routine DIFFUS for calculation of a smoothing operator used to reduce the effort of non linear instabilities arising from non linear terms in the continuity equations.

Tables and Items

No major variables are used in ADVECT which have not been previously defined.

2.3.3.8

Subroutine DIFFUS

Subroutine DIFFUS is used to calculate small diffusion terms which are used to reduce instabilities within the non linear continuity equation.

Inputs

All required input for DIFFUS is input to the routine by ADVECT through the formal parameter list. Major input variables are defined under ICEMDL. Any important functions performed by these variables in DIFFUS are detailed below.

Processing

Subroutine DIFFUS applies a simple smoothing operator to obtain a small diffusion term for the respective field being analyzed. This term is applied to the results of the computations of the dynamical portions of the continuity equations.

Output

The diffusion terms are stored in the third level of the array, HEFF.

Interfaces

No major subroutines are accessed by DIFFUS.

Tables and Items

Subroutine DIFFUS introduces no previously defined variables.

2.4.3.9

Subroutine HEAT

Subroutine HEAT is the driving routine for the heat budget code. This budget solves for the thermodynamic growth rate of the thick and thin ice.

Input

Subroutine HEAT receives all input variables from ICEMDL, through the formal parameter list.

Subroutine HEAT also accesses the CRANDIO data base which contains the FNOC environmental data. The following data records are accessed;

- i) air temperature;
- ii) surface pressure;
- iii) surface vapor pressure;
- iv) incoming solar radiation;
- v) sensible heat flux;
- vi) sensible plus evaporative heat flux.

The data is read from the CRANDIC file through the use of subroutine INITIAL of the input module.

Processing

The primary function of subroutine HEAT is to set up all necessary variables for the heat budget calculations, performed in subroutine BUDGET.

The wind data is calculated in the first main loop of HEAT. This variable is calculated from GAIRX and GAIRY which contain the u and v components respectively.

Subroutine INITIAL is called to read the air temperature data at the surface from the CRANDIO data base. Subroutine AVG is called to compute the grid cell average of the air temperature data. Subroutine AVG is used for all thermodynamic variables, within HEAT to define them within the staggered grid. The temperature data is finally converted from centigrade to Kelvin.

Subroutine INITIAL and AVG are again used to define the atmospheric surface pressure and vapor pressure. These variables are used to calculate the moisture at the surface which is stored within QA.

Subroutine INITIAL is finally used to retrieve the shortwave radiation, sensible heat flux and sensible plus evaporative heat flux. The variables are converted from the CGS system to the MKS system and used to calculate the incoming longwave radiation. At the end of the processing the following variables have been set up for use in BUDGET;

- i) TAIR - air temperature;
- ii) QA - surface moisture;
- iii) FSH - incoming shortwave radiation;
- iv) FLC - incoming longwave radiation.

The final preparation before BUDGET is called is the definition of the mixed layer depth (HMX) plus the temperature of the mixed layer and temperature of the ice, TMIX and TICE respectively.

The variable, KOPEN, is used as a flag to BUDGET to determine whether thin ice or thick ice growth rates are evaluated. Subroutine BUDGET is then called to calculate the growth rate of each category. The

total growth rate is then calculated and stored in FHEFF.

Output

The environmental parameters listed under the Tables and Items section are output from HEAT.

Interfaces

Subroutine HEAT interfaces with two main subroutines, INITIAL and BUDGET. Subroutine INITIAL is used to retrieve data from the CRANDIC data base and BUDGET is used to calculate the thin and thick ice growth. The parameter list for INITIAL is defined as follows;

- i) parameter 1 - number, indicating which catalog name is to be used in INITIAL;
- ii) parameter 2 - array used to store the environmental data returned from INITIAL;
- iii) parameter 3 - i grid points of the grid;
- iv) parameter 4 - j grid points of the grid;
- v) parameter 5 - DTG required;
- vi) parameter 6 - number of points in the grid;
- vii) parameter 7 - tau value.

The parameter list of BUDGET is defined
as follows;

- i) parameter 1 - ice thickness;
- ii) parameter 2 - growth rate returned
to HEAT;
- iii) parameter 3 - flag used to de-
termine whether thin
or thick ice growth
is calculated;
- iv) parameter 4 - grid size;
- iv) parameter 5 - grid size;
- v) parameter 6 - wind data;
- vi) parameter 7 - ice temperature;
- vii) parameter 8 - mixed layer tempera-
ture;
- viii) parameter 9 - air temperature;
- ix) parameter 10- surface moisture;
- x) parameter 11- incoming longwave.

Tables and Items

The following new major variables are
defined in HEAT;

- i) TICE - ice temperature;
- ii) TMIX - mixed layer temperature;
- iii) TAIR - air temperature;
- iv) QA - surface moisture;
- v) FLO - incoming longwave
radiation;
- vi) PS - surface pressure and sen-
sible heat flux;
- vii) CS - surface vapor pressure and
sensible plus evaporative
heat flux;
- viii) UG - wind values.

The following common block is defined:

/RAD/ - contains incoming shortwave radiation.

2.4.3.10

Subroutine BUDGET

Subroutine BUDGET is used to calculate the thin and thick ice growth rates by using a simple heat budget.

Input

Subroutine BUDGET receives all major input variables from HEAT. Most of these are passed through the formal parameter list. One variable, FSH, is passed in common block /RAD/.

Processing

The initial code of BUDGET is dedicated to defining all necessary constants used in the heat budget calculations.

A branch is made, depending upon the value of KOPEN. If KOPEN is less than zero, processing continues to compute the thin ice growth rate. If KOPEN is greater than zero processing jumps to compute the thick ice growth rate.

Continuing with the the ice growth, the main heat budget equation components, and growth rate derived within loop 101. Subroutine BUDGET ends processing here for this branch.

When the thick ice growth rate is computed, there are two main components of the heat budget calculation. The ice temperature, TICE, is solved for iteratively (Newton-Raplsn technique) and used in the head budget equation. When the ice temperature values are relatively stable between iterations, processing finishes returning the thick ice growth rate.

Output

The output of BUDGET is contained in the following variables;

- i) FHEFF - thick ice growth rate;
- ii) FO - thin ice growth rate.

Interfaces

Subroutine BUDGET calls no other sub-routines.

Tables and Items

The variable, ALB, defining the surface albedo, is the only major variable not previously defined and used within BUDGET.

2.4.3.11

Subroutine GROWTH

Subroutine GROWTH is used to calculate the change in ice thickness amd concentration due to growth/decay.

Input

All required input variables to GROWTH are passed from ICEMDL through the formal parameter list. No variables, not previously defined, are input to GROWTH.

Processing

The processing of GROWTH is contained in one major loop. The amount of ice grown and melted during the time step. The changes, reflected by the growth/decay rates, are added to the ice thickness, HEFF, and ice concentration, AREA, variables. The ice concentration value is then checked to contain it within the limits specified. Ice concentrations are not allowed to be larger than 1.0.

Output

The variables HEFF, AREA and GAREA contain output variables of GROWTH.

Interfaces

No other subroutines are called by GROWTH.

Tables and Items

No new variables are introduced by GROWTH.

2.4.3.12

Subroutine ADJUST

Subroutine ADJUST is used to set up the thickness and concentration at the outflow cells.

Input

All input variables, to ADJUST are passed from ICEMDL through the parameter list. No variables not previously defined are used.

Processing

Subroutine ADJUST is called at the end of each time step. ADJUST uses routine MEAN to calculate the ice in the open cells by taking an average of all grid cells adjacent to the open boundary. The ice thickness and concentration arrays are both modified in this manner.

Outputs

The arrays HEFF and AREA (ice thickness and ice concentration) are respectively modified.

Interfaces

Subroutine ADJUST calls subroutine MEAN to calculate the ice in open grid cells.

Tables and Items

No major new variables are defined.

2.4.3.13

Subroutine MEAN

Subroutine MEAN is used to calculate the amount of ice in open cells.

Input

All data input to MEAN is passed by ADJUST through the parameter list. No new variables are introduced as input.

Processing

Subroutine MEAN calculates the amount of ice in a grid cell as the mean of ice in the adjacent cells. Array CUT, which is the boundary mask specifying the outflow cells, is used to control the calculations to output the mean ice held within the outflow cells.

Output

The variable, HMEAN, is output to ADJUST, containing the mean ice thickness and concentration on the open cells.

Interfaces

No other subroutines are called by MEAN.

Tables and Items

No new major variables are introduced by MEAN.

2.4.4

Output Module

2.4.4.1

Subroutine DIVERG

Subroutine DIVERG is used to output the divergence values to the CRANDIO output file.

Input

All required input variables are supplied to DIVERG from ICEMDL through the formal parameter list. No new variables are input.

Processing

Subroutine DIVERG operates like all output module subroutines. Major processing functions are performed for the sole purpose of setting up the data and appropriate record names for the CRANDIC data base.

The data is placed into the common block array DIVERG. The record label is set up using a data statement which specifies the catalog name, tau value and record length.

If an error occurs on the CWRITER function an error message is written, stating this fact and the program will terminate.

Output

Subroutine DIVERG places the divergence values on the CRANDIO output file.

Interfaces

Subroutine DIVERG interfaces with the standard FNOC CRANDIO software.

DIVERG is called on every fourth time step by ICEMDL.

Tables and Items

The following common block is defined;

/DV/ - MDV - contains CRANDIO ID block;
DIVERG - contains data values;
FILLV - fills the small page (requirement of CRANDIO).

2.4.4.2

Subroutine UVPLOT

Subroutine UVPLOT is used to output the ice drift forecasts.

Input

All input to UVPLOT is provided by ICEMDL, through the parameter list. No new variables are introduced.

Processing

The first main function of UVPLOT is to convert the U, V ice drift components to ice drift direction and speed. This is accomplished through the FNOC routine UVDDFF. Ice drift speed is converted from m/sec to knots.

The final function is setting up of the CRANDIO record labels for CRANDIC. The record labels are set up using a data statement containing the catalog names, tau values and record lengths.

If an error occurs on the CWRITER function, a message is written and the program terminates.

Output

The ice drift direction and speed is output to the final CRANDIO file.

Interfaces

UVPLOT interfaces with the FNOC CRANDIC software. UVPLOT is called on every fourth time step by ICEMDL.

Tables and Items

No new major variables are introduced by UVPLOT.

2.4.4.3

Subroutine BUOYD

Subroutine BUOYD is used to calculate the drift of simulated buoys placed in the model.

Input

All input required for BUOYD is supplied by ICEMDL through the parameter list. No new variables are introduced by BUOYD.

The buoy drift positions are input through common block /BUOY/.

Processing

The initial processing of BUCYD checks the position of each buoy. This is done to determine if a buoy has moved out of the grid. Once a buoy reaches a boundary it is no longer tracked. The routine branches around the remainder of the processing and goes on to another buoy when one has moved to the boundary.

Subroutine INTRP, a FNOC utility routine, is used to interpolate the U, V ice drift components to the buoy position recorded during the previous time step. The u, v values are then used to calculate how far the buoy shall have moved during the current time step. This distance is then determined in terms of grid units on both the model grid and the FNOC hemispheric grid.

The final position of each buoy, in terms of both grid, is printed in a table.

Output

The positions of the buoys, calculated in common block /BUOY/ are output from BUOYD a printed table, outlining the position of each buoy is provided.

Interface

BUOYD utilizes the FNOC utility routine INTRP to provide u, v components of ice drift at buoy positions.

Tables and Interfaces

BUOYD. No new variables are introduced within

2.4.4.4 Subroutine HAPLOT

Subroutine HAPLOT is used to output the ice thickness and concentration values to the CRANDIC file.

Input

All required input to HAPLOT is provided by ICEMDL through the formal parameter list. No new input variables are defined.

Processing

Processing within HAPLOT performs two functions. The first is a unit conversion while the second creates the necessary data for CRANDIC. Ice thickness is output first. The thickness values are converted from meters to cm. The CRANDIC record labels and data are set up into their respective positions and CWRITER is used to write the data.

The ice concentration values are handled in the same manner. However no unit conversion is performed.

If an error results in the processing of any CWRITER an appropriate message is written and the program shall terminate processing.

Output

The ice thickness and compactness values are output to the CRANDIO file.

Interfaces

HAPLOT interfaces with the CRANDIO software.

Tables and Items

No new major variables are introduced.

2.4.4.5

Subroutine GROWDEC

Subroutine GROWDEC is used to output the open water growth and ice growth forecasts.

Input

All required input is passed to GROWDEC by ICEMDL.

Processing

The processing of GRCWDEC proceeds exactly as other output module subroutines. The CRANDIO labels are defined and CWRITER is used to output the data.

Output

Forecasts of open water and total ice growth are written to the CRANDIO file.

Interfaces

GROWDEC interfaces with the CRANDIO software.

Tables and Items

Nom new variables are defined.

2.4.4.6

Subroutine PRNT

Subroutine PRNT is a small subroutine which is used to print model arrays. The processing of PRNT depends entirely upon the input data specifications.

Input

The formal parameters are defined as follows;

- i) ARRAY - array to be printed;
- ii) I,J,K - dimensions of ARRAY;
- iii) MI,MZ - columns of ARRAY which are printed;
- iv) N - number of rows of ARRAY to be printed.

Output

Printed output of a data array is provided.

Section 3.0

Environment

3.1

Equipment Environment

FNOC operates a multiprogramming/-multi-- mainframe computer system consisting of three CDC 6500's, with 131K each of central memory (CM), 9 CDC CYBER 170/175 with 196K CM and 1 million words of CDC 7030 extended core storage (ECS), related auxiliary equipment (7 and 9 track tape units, disk storage, etc.), a CYBER 203 with 2 million words of CM and its front-end processor CYBER 170/720, and a VARIAN plotter and its plotting software. The Sea Ice model is designed to run on the CYBER 203 computer, and its output is plotted on the VARIAN plotter.

3.2

Support Software

FNOC operates under the NOS/BE operating system. This system contains many local enhancements/modifications to facilitate ease of operation. Most of the enhancements are documented in either the FNOC subroutine/utility file or the FNWC Computer User Guide Edition 2. The Sea Ice Model was converted to CDC CYBER 200 FORTRAN Language, version 1.5 and utilizes various routines available on FNWCLIB.

3.3

Data Base

A number of data bases are maintained and needed by the sea ice model.

3.3.1

General Characteristics

Three separate input data bases are required for the sea ice model to properly execute. Two of these are created by the user. The third data base consists of the FNOC environmental data. Currently this data is not operationally available on the CY203, therefore, this data base is also set up by the user, from data available on other machines.

i) TAPE7

TAPE7 is the mnemonic for the main input file. This file is set up by a user and remains permanent for the desired configuration of the model runs.

The file is utilized by the input module and describes the execution configuration for the current run (e.g., grid size, grid location, grid configuration).

ii) TAPE8

TAPE8 is a more dynamic data file than TAPE7. TAPE8 contains the DTG's of the days during the current run. Therefore, this file will change for each run.

The file, TAPE8, needs to be defined by the user of the sea ice model.

iii) FNOC Data

FNOC data is kept on a CRANDIO file which, at the time of this writing, must be set up by the user. These data will change for a specific run. The data is obtained from another machine which has access to the FNOC master data base (MASFNWC).

iv) Output Data-Base

A CRANDIC output data base is maintained by the sea ice model. This data base is filled with forecast variables computed by the sea ice model. Variables are written in specified time steps, defined in routine ICEMDL.

3.3.2

Organization and Detailed Description

i) TAPE7

The file labeled TAPE7 is a binary file accessed by a formatted READ. The following information is contained, with formats;

- i) grid size specifications - 2I5;
- ii) FNOC i grid points for MESH - 2F10.2;
- iii) FNOC j grid points for MESH - 2F10.2;
- iv) number of rows/columns in model grid - I5
- v) uv boundary mask - 27F2.0, 27 rows
- vi) thickness boundary mask - 28F2.0, 28 rows;
- vii) outflow boundary mask - 28F2.0, 28 rows;
- viii) ocean current direction - 25F3.0, 25 rows.

ii) TAPE8

The file labeled, TAPE8, is a binary

file accessed with a formatted READ. The following information is contained, with formats;

- i) number of time steps to be run -
I5;
- ii) DTG, one row for each time step
3(A8,2X).

The DTG rows are defined as described under ICEMDL.

iii) FNOC Input Data

The input FNOC data base is a CRANDIO data file on the CY203. CRANDIO is the operational data file format, specified by FNOC, on the CY203. Detailed characteristics of the CRANDIO files can be found in the CRANDIO software documentation distributed by FNOC.

The data on the CRANDIO file is created by transferring ZRANDIO data, from other FNCC machines to the CY203 with proper ZRANDIO to CRANDIO conversion software.

The following records are contained on the CRANDIO input file;

<u>Record</u>	<u>Contents</u>
A20	u-wind component
A21	v wind component
A10	air temperature
A01	surface pressure
A12	surface vapor pressure
A11	short wave radiation incoming
A18	total heat flux
A16	sensible plus evaporative heat flux.

iv) CRANDIO Output File

The CRANDIO output file is created by the sea ice model. CRANDIC records are written consisting of forecast variables on certain time steps. The following records are written every four time steps;

<u>Record</u>	<u>Contents</u>
i) DIV	ice divergence/convergence
ii) FFF	ice drift speed
iii) DDD	ice drift direction
iv) THK	ice thickness
v) COM	ice concentration
vi) PRS	ice pressure
vii) GAR	open water growth
viii) HDF	ice growth.

Section 4.0 Program Maintenance Procedures

4.1 Conventions

The Sea Ice Model system adheres to structured design and programming principles. Flowcharting and naming conventions adhere to the standard identified below.

- a. FNWC User Guide, Edition 2,
February, 1974.
- b. CDC Programming Standards, CDC-STD
1.80.000, December, 1971.

4.2 Verification Procedures

The methods of verifying the sea ice model output through display of the output file on plotting display or printed output. Plotting of ice drift, ice growth/decay rate, ice thickness is a very efficient method used to check output of the model.

4.3 Error Conditions

This section describes the error conditions determined by the Sea Ice Model.

ICEMDL

Message - "OPEN ERROR"
Reason - error in opening the
CRANDIC output file

RELAX

Message - "No convergence after 1300 iterations"

Reason - UICE and VICE are not convergent after 1300 iterations.

UVPLOT

Message - "STATUS is (value) ON WRITE OF filename"

Reason - ISTAT is not equal to 0.

Result - Output of UVPLOT is not written to CRANDIC file, program stops.

HAPLOT

Message - "STATUS IS (value) ON WRITE OF filename"

Reason - ISTAT is not going to 0.

Result - Output of HAPLOT is not written to CRANDIO file, program stops.

DIVERG

Message - "CWRITE STATUS IS (Value) ON WRITE OF filename"

Reason - ISTAT is not equal to 0, the CRANDIO output file is not opened.

Result - Output of DIVERG is not written to CRANDIO file, program stops.

INITIAL

Message - "CHECKNC no data initial"
Reason - No required data field for
input
Result - Stop the program.

4.4

Special Maintenance Procedures

There are no special maintenance procedures for the Sea Ice Model program.

4.5

Special Maintenance Programs

There are no special maintenance programs for the Sea Ice Model.


4.6


Listings


Listings of the Sea Ice Model program and subroutines are to be found in Appendix C.


APPENDIX A


ICEMDL Flowcharts






























Finite differences
for RELAX as a
function of current
U.V.





Finite differences
for main interaction
process in RELAX








































AD-A114 343

CONTROL DATA CORP MONTEREY CA F/G 8/12
PROGRAM MAINTENANCE MANUAL POLAR ICE FORECAST SUBSYSTEM - ARCTI--ETC(U)
OCT 81 P A HARR, T C PHAM, J P WELSH N00014-81-F-0028
NORDA-TN-122 ML

UNCLASSIFIED

2 of 2
A114 343





Appendix B

Grid Structure

The model grid is set up in a staggered manner. Momentum variables are defined at the grid points while thermodynamic variables are defined for grid cells.

Environmental variables accessed from the FNOC data base are computed to be valid at the grid cell locations. Subventive AVG is used to compute the grid cell averages for the thermodynamic variables.

The following example illustrates the definition of grid parameters for a small grid.

Say, we define NX,NY to be 7 (dimension of momentum variable grid). Figure B1 illustrates that NX1,NY1 (thermodynamic grid) will be 8 while the value of NUMBER will be 9.




Figure B1 Grid Configuration

APPENDIX C

ICEMDL Listings

TRAN 1.5.1 CYCLE FINISH BUILT 04/03/81 23 27 SOURCE LISTING TCE:DL

```

*      0.0. 32.4/
00014      DATA _AD,ICOUNT,TOUT,HFSUM,JVSUM,HFSUM/0.0,0.0,400.0/
00019      DATA DELTAT,DELTT,FR200,FHSMJ,GRSJMI,APSJMI,APS,47/2*45400.1,
*      0.000001,3*0.0, 0.15, 0.5/
00020      CALL SECOND(THESIV)
00021      READ (2,13) ITSTEP
00022      READ (7,13) NX,NY,NXI,NYI,N3,V4
00023      13      FORMAT(4I5)
00024      PRINT 10000, NX,NY,NXI,NYI,N3,V4
00025      10000  FORMAT(1X,10I10,GRJ 1,4I5)
C
C NOW DECIDE ON BASIC PARAMETERS
C
00026      READ (2,14) INT3(1), INT3(2), INT3(3)
00027      14      FORMAT(4I5,2X,4I5,2X,4I5)
00028      CALL MESH(320,320,NX,NY,NXI,NYI,NUM400)
00029      FR200=0.05*FR200
00030      DIFF1=0.02*DELTTAX
00031      DIFF1=2.0*DIFF1
C
C DOUBLE 40 BECAUSE OF 400 IN GROWTH
C
00032      40=2.0*40
C
C NOW DEFINE BOUNDARIES
C
00033      CALL BOUNDY(HFSUM,JVM,OUT,NX,NY,NXI,NYI)
00034      DO 122 I=1,NY
00035      DO 122 J=1,NXI
00036      HFSUM=HFSUM+OUT(I,J)
00037      HFSUM=HFSUM+HFSUM(I,J)
00038      122 CONTINUE
00039      DO 125 I=1,NY
00040      DO 125 J=1,NX
00041      JVSUM=JVSUM+JVM(I,J)
00042      125 CONTINUE
00043      PRINT 4,HFSUM,JVSUM
00044      PRINT 4,HFSUM,JVSUM
00045      FORMAT(1X,4HFSUM 15F,615,4,4JVSUM 15F,615,7)
C
C FORM OCEAN CURRENTS
C
00046      CALL OCEAN(OMATX,OMATY,NX,NY,GRJI,GRJY,JVM)
C
C OPEN THE OCEANIC OUTPUT FILE
C
00047      IFILE = OUTPFC
00048      CALL OPEN(IFILE,ISTAT)
00049      IF(ISTAT.NE.0) STOP 'OPEN ERROR'
00050      ITAU = 0
00051      MSH = MESH5
00052      CALL SECOND(MESH5)
00053      MESH5 = MESH5 - MSH
C
C OBTAIN THE INITIAL MINO VALUES
C
00054      LSTEP = 0
00055      CALL INITIAL(1,GRJX,GRJI,GRJY,INT3,NUM400,ITAU)
00056      CALL INITIAL(2,GRJY,GRJI,GRJY,INT3,NUM400,ITAU)

```

TRAN 1.5.1 CYCLE FINISSE BUILT 04/03/74 23 27 SOURCE LISTING

ICEADL

```

00057 C CONVERT WINDS FROM CM/SEC TO M/SEC
00058 NP = NX + 2
00059 DO 10 I = 1,NP
00060 DO 10 J = 1,NP
00061 GAIRX(I,J) = GAIRX(I,J) / 100.0
00062 GAIY(I,J) = GAIY(I,J) / 100.0
00063 CONTINUE
10
C
C NOW INITIALIZE SYSTEM
C FIRST GUESS AT INITIAL HFFF AND AREA
C
00064 DO 12 I = 1,NY
00065 DO 12 J = 1,NX
00066 HICE(I,J) = 0.0
00067 HICE(I,J) = 0.0
00068 CONTINUE
12
00069 DO 14 K = 1,3
00070 DO 14 J = 1,27
00071 DO 14 I = 1,27
00072 HICE(I,J,K) = 0.0
00073 HICE(I,J,K) = 0.0
00074 CONTINUE
14
00075 DO 101 J = 1,29
00076 DO 101 I = 1,24
00077 HFFF(I,J,1) = 0.0
00078 HFFF(I,J,2) = 0.0
00079 AREA(I,J,2) = 1.0
00080 AREA(I,J,3) = 1.0
00081 HFFF(I,J,1) = (3.0) / 7.9
00082 HFFF(I,J,1) = HFFF(I,J,1) * OUT(I,J)
00083 AREA(I,J,1) = 1.0
00084 CONTINUE
101
C
C CALCULATE TOTAL BASIN ICE THICKNESS
C EXCEPT AT OUTFLOW CELLS
C
00085 CALL SUM(HFFF,THFF,NX,NY)
00086 THET = 1.0
C
C START WITH AN INITIAL VELOCITY FIELD OF ZERO
C
00087 CALL FORA(HICE,VICE,ETA,ZETA,AMASS,GAIRX,GAIRY,GHATX,GHATY,
* DRAG,DRAG0,DJT,HFFF,NX,NY,NX,NY),DIV,HFFF,AREA)
C
C SET MASS TO 0 AND DEFINE THE VISCOSITIES
C
00088 DO 103 J = 1,27
00089 DO 103 I = 1,27
00090 AMASS(I,J) = 0.0
00091 ZETA(I,J) = HFFF(I,J,1) * (1.0E+11)
00092 ETA(I,J) = ZETA(I,J) / 4.0
00093 CONTINUE
103
C
00094 CALL RELAX(HICE,VICE,ETA,ZETA,DRAG,DRAG0,AMASS,DJM
* DRAG,THETA,DJT,HICE,VICE,HFFF,NX,NY,NX,NY)
00095 DJT = 2.0
00096 PRINT(140,HICE AND VICE AFTER FIRST RELAX *)

```

```

000000      SUBROUTINE ADJUST-
000000
000000      THICKNESS AND COMPACTNESS VALUES AT THE OUTFLOW CELLS ARE
000000      ESTIMATED USING SURROUNTING MEAN.
000000      ALL ICE FLOWING INTO THE GRID THROUGH THE OPEN CELLS IS
000000      ACCOUNTED FOR.
000000
000000      THEFF1 CONTAINS THE AMOUNT OF ICE IN THE OUTFLOW CELLS....
000000      THIS IS USED IN THE ADVECTION CALCULATIONS.
000000
000096      CALL ADJUST(HEFF,AREA,OUT,HEFF4,NX,NY,NX1,NY1)
000000
000000      NOW START THE STANDARD PREDICTOR-CORRECTOR ITERATION SCHEME
000000
000097      CALL SECOND(TNEW)
000098      TT = TNEW - TRESIN
000099      PRINT 2122,TT
000100      2122 FOR AT(140,*****) INITIALIZATION TIME 0.510.4)
000101      100 CONTINUE
000102      CALL SECOND(TNEW)
000103      CALL XSIN(HEFF,THEFF1,NX1,NY1)
000104      THEFF1 = THEFF1 - THEFF
000000
000000      FIRST DO THE PREDICTOR
000000
000105      DO 121 J=1,NY
000106      DO 121 I=1,NX
000107      UICE(I,J,3)=UICE(I,J,1)
000108      VICE(I,J,3)=VICE(I,J,1)
000109      UICE(I,J)=UICE(I,J,1)
000110      VICE(I,J)=VICE(I,J,1)
000111      121 CONTINUE
000112      THETA=1.0
000113      DELTAT=DELTT/2.0
000114      1000 CONTINUE
000115      CALL FORM(UICE,VICE,ETA,ZETA,AMASS,GAIRX,GAIRY,GNATX,GNATY,
000116      * DRASS,DRAGA,OUT,HEFF4,NX,NY,NX1,NY1,DTV,HEFF,AREA)
000116      CALL RELAX(UICE,VICE,ETA,ZETA,DRASS,DRAGA,AMASS,JVM
000117      * FPROR,THETA,UICE,VICE,HEFF4,NX,NY,NX1,NY1)
000000
000000      NOW DO REGULAR TIME STEP
000000
000117      1001 CONTINUE
000118      THETA=1.0
000119      DELTAT=DELTT
000120      CALL FORM(UICE,VICE,ETA,ZETA,AMASS,GAIRX,GAIRY,GNATX,GNATY,
000121      * DRASS,DRAGA,OUT,HEFF4,NX,NY,NX1,NY1,DTV,HEFF,AREA)
000000
000000      NOW SET U(1)=U(2) AND SAME FOR V
000000
000121      DO 111 J=1,27
000122      DO 111 I=1,27
000123      UICE(I,J,3)=UICE(I,J,1)

```

RTNAN 1.5.1 CYCLE FTV1554 BUILT 09/03/91 23 27 SOURCE LISTING TCEMOL

```

00124      VICE(I,1,3)=VICE(I,J,1)
00125      VICE(I,1)=VICE(I,J,1)
00126      VICE(I,1)=VICE(I,J,1)
00127      VICE(I,1,1)=VICE(I,J,2)
00128      VICE(I,1,1)=VICE(I,J,2)
00129      111 CONTINUE
00130      CALL RELAX(VICE,VICE,ETA,ZETA,DRAGS,DRAG4,AMASS,IVV
&.SPROD,THETA,VICE,VICE,HEFF4,NX,NY,NX1,NY1)

C
C
00131      ITOINT=ITOUT+1

C
00132      S01 = 0.0
00133      S0 = 0.0
00134      S41 = 0.0
00135      SVM = 0.0
00136      D0130 J = 1.0Y
00137      D0130 I = 1.0Y

C
C      SAVE THE T+1 TIME VALUES OF U AND V FOR USE IN ADVECTION OF
C      THE THICKNESS AND COMPACTNESS.
C
00138      VICE(I,1) = VICE(I,J,1)
00139      VICE(I,1) = VICE(I,J,1)

C
C      CALCULATE THE SQUARED VELOCITY AND THE SQUARED VELOCITY DIFFERENCE
C      BETWEEN TIMES T + 1 AND T
C
00140      S1 = S0 + VICE(I,1,1)**2 + VICE(I,J,1)**2
00141      IERR = VICE(I,J,1) - VICE(I,J,2)
00142      VERR = VICE(I,1,1) - VICE(I,J,2)
00143      S01 = S01 + (IERR * IERR) + (VERR * VERR)
00144      S41 = AMAX1(ABS(IERR),S41)
00145      SVM = AMAX1(ABS(VERR),SVM)
00146      140 CONTINUE
00147      S4 = AMAX1(S41,SVM)

C
C      PRINT THE VELOCITY INFORMATION
C
00148      PRINT 11,ITOUT,ITIS(1)
00149      11 FORMAT(1-1,THE TIME STEP IS 1.1,THE DATE IS 1.4)
00150      2 FORMAT(20,(* 8.5520,14))
00151      PRINT 2
00152      PRINT 3,S0,S01,S4
00153      3 FORMAT(* 8.5520 VELOCITY, S0, VELOCITY DIFFERENCE,
& MAX CHANGE 8.78 8.5520,12)

C
C      IF(LESTP,NF,3) GO TO 547
00154      CALL DIVERG(DIV,NX,NY,GRD1,GRD2,ITIS,ITAM)
00155      CALL IMPLT(VICE,VICE,ITIS,NX,NY,GRD1,GRD2,ITAM)
00156      412 CONTINUE
00157      CALL RIDYD(VICE,VICE,GRD1,GRD2,NX,NY)

C
C      DO ADVECTION
C
C      CALCULATE THE ADVECTION OF ICE THICKNESS AND COMPACTNESS
C
00158      CALL ADVECT(VICE,VICE,HEFF,DIEF1,LA),HEFF,NX,NY,NX1,NY1)
00159      145 CALL ADVECT(VICE,VICE,AREA,DIEF1,LA),HEFF,NX,NY,NX1,NY1)

```

RTNAN 1.5.1 CYCLE FTV1554 411LT 04/03/91 23 27 SOURCE LISTING 105M1
 NOW DO THE GROWTH COMPONENT

SUBROUTINE HEAT CALCULATES THE GROWTH RATES FOR ICE AND OPEN
 WATER.... USING A HEAT BUDGET.

00151 CALL HEAT(GROW,GRJ,HEFF,AREA,FO,FHEFF,GAIRX,GAIRY,ITAU,ITIS,
 * NY1,NY1,NJMPER)
 00152 CALL GROWTH(HEFF,AREA,H0,AP2,FHEFF,FO,H0CORR,HEFF4,OUT,NY1,NY1,GRJ,
 *A)

MUST CALL GROWTH ONLY AFTER CALLING ADVECTION

SUM OF TOTAL ICE IN THE BASIN... EXCLUDING OUTFLOW CELLS

00153 CALL XSUM(HEFF,THEFF,NX1,NY1)

THIS SECTION COMPUTE VARIOUS SUMS NECESSARY FOR INSURING
 CONSERVATION PLUS MONITORING VARIOUS CONTRIBUTIONS TO ICE
 CHANGES.

00154 GR = 0.0
 00155 THEFF2 = 0.0
 00156 FHSUM = 0.0
 00157 GRSUM = 0.0
 00158 ARSUM = 0.0
 00159 FHEF = 0.0
 00170 DO 105 I = 1,24
 00171 DO 105 J = 1,23
 00172 HEFF(I,J,1)=HEFF(I,J,1)*OUT(I,J)
 00173 AREA(I,J,1)=AREA(I,J,1)*OUT(I,J)
 00174 FHEFF(I,J)=FHEFF(I,J)*OUT(I,J)

HDIFF CONTAINS THE TOTAL OPEN WATER GROWTH FOR THE BASIN

00175 HDIFF(I,J) = (1.0 - AREA(I,J,2)) * FO(I,J) * OUT(I,J) * DELT
 00176 GRSUM = GRSUM + HDIFF(I,J)
 00177 THEFF2 = THEFF2 + HEFF(I,J,1)
 00178 ARSUM = ARSUM + AREA(I,J,1)
 00179 FHSUM = FHSUM + FHEFF(I,J)
 00180 105 CONTINUE
 00181 GRSUM1=GRSUM+GRSUM

GRSUM1 CONTAINS THE NET OPEN WATER GROWTH

00182 FHSUM1=FHSUM1+FHSUM

FHSUM1 CONTAINS THE NET ICE GROWTH

00183 ARSUM1=ARSUM1+ARSUM
 00184 TOUT1=THEFF-THEFF2-THEFF
 00185 THEFF=THEFF2
 00186 TOUT=TOUT+TOUT1

OUTPUT SECTION..... PRINT ON SPECIFIED TIME STEPS

00187 65 CONTINUE
 00188 IF(LSTEP.NE.3) GO TO 547
 00189 6 FORMAT(//)

```

RT-AN 1.5.1 CYCLE FINISHES 401LT (P/04/4) 22 27 SOURCE LISTING TCFM JL
00190 1 FORMAT(8,'TIME STEP AND TOTAL THICKNESS APPR.10,10X,2),12)
00191 PRINT 21,1013(1)
00192 41 FORMAT(141,'IT H I O K H E S S THE DATE IS 1,6-1)
00193 PRINT 1,100UNT,THEFF1
00194 PRINT 1,100UNT,THEFF
00195 PRINT 4
00196 PRINT 2,100T1,100T
00197 PRINT 4
00198 2 FORMAT(1X,100TLOW FOR THIS TIME STEP 1,F10.4/1X,
*10ET 10TLOW 1,F10.4)
00199 3 FORMAT(1X,100EN WATER GROWTH 1,F10.4/1X,
*10ET 100EN WATER GROWTH 1,F10.4)
00200 4 FORMAT(1X,100F GROWTH FOR THIS TIME STEP 1,F10.4/
*1X,100F 10F GROWTH 1,F10.4)
00201 CALL H0010T(HFFF,APFA,1013,1013,22,1,6X,6Y)
00202 CALL G00000(H01FF,THEFF,300FA,1013,1013,1,6X,1,6Y)
00203 PRINT 4
00204 44 CONTINUE
00205 PRINT 1,100UNT,THEFF
00206 PRINT 2,100T1,100T
00207 PRINT 3,F45J1,F45J1
00208 PRINT 4,325J1,325J1,425J1,425J1
00209 PRINT 417
00210 517 FORMAT(140,100EN WATER GROWTH)
00211 CALL PRINT(H01FF,24,24,1,1,13,24)
00212 CALL PRINT(H01FF,24,24,1,14,24,24)
00213 PRINT 500
00214 520 FORMAT(140,100F AND VICE)
00215 CALL PRINT(100F,27,27,3,1,13,27)
00216 CALL PRINT(100F,27,27,3,14,24,27)
00217 CALL PRINT(VICE,27,27,3,1,13,27)
00218 CALL PRINT(VICE,27,27,3,14,24,27)
00219 PRINT 501
00220 521 FORMAT(140,14FFF)
00221 CALL PRINT(HFFF,24,24,3,1,13,24)
00222 CALL PRINT(HFFF,24,24,3,14,24,24)
00223 PRINT 502
00224 522 FORMAT(140,14DEA)
00225 CALL PRINT(APFA,24,24,3,1,13,24)
00226 CALL PRINT(APFA,24,24,3,14,24,24)
00227 PRINT 503
00228 527 FORMAT(140,154 TERM)
00229 CALL PRINT(FHFFF,24,24,1,1,13,24)
00230 CALL PRINT(FHFFF,24,24,1,14,24,24)
00231 PRINT 504
00232 529 FORMAT(140,153 TERM)
00233 CALL PRINT(GADEF,24,24,1,1,13,24)
00234 CALL PRINT(GADEF,24,24,1,14,24,24)
00235 PRINT 505
00236 537 FORMAT(140,100F TO BE MELTED TO MAINTAIN MASS BALANCE)
00237 CALL PRINT(H0022,24,24,1,1,13,24)
00238 CALL PRINT(H0022,24,24,1,14,24,24)
00239 PRINT 541
00240 541 FORMAT(140,100F STRENGTH N/M)
00241 CALL PRINT(POFSS,24,24,1,1,13,24)
00242 CALL PRINT(POFSS,24,24,1,14,24,24)
00243 PRINT 542
00244 542 FORMAT(140,100F DIVERGENCE FIELD SFC-1)
00245 CALL PRINT(DIV,24,24,1,1,13,24)
00246 CALL PRINT(DIV,24,24,1,14,24,24)

```

STAN 1.5.1 CYCLE FINISH4 BUILT 04/03/81 23 27 SOURCE LISTING

ISEMIL

```

00247 547 CONTINUE
      C
      C      CALL ADJUST TO ESTIMATE THE ICE IN THE OUTFLOW CELLS
      C
00248      CALL ADJUST(HEFF,ARPA,OUT,HEFFM,NX,NY,NA),NY))
      C
      C      DETERMINE IF THE ITERATION PROCESS CONTINUES
      C
00249      CALL SECOND(TP)
00250      TT = TP - TNEW
00251      PRINT 3123,TT
00252 3123  FORMAT(1H0,0000000000 TIME STEP TIME    1.F10.4)
00253      IF(TCOUNT .EQ. ITSTEP) GO TO 205
      C
      C      CHECK IF NEW INPUT DATA IS REQUIRED
      C
00254      LSTEP = LSTEP + 1
00255      IF(LSTEP .NE. 4) GO TO 100
00256      LSTEP = 0
00257      READ(2,14) INTG(1), INTG(2), INTG(3)
00258      CALL INITIAL(1,GAIRX,GR01,GR0J,INTG,NUMREP,ITAI)
00259      CALL INITIAL(2,GAIRY,GR01,GR0J,INTG,NUMREP,ITAI)
00260      DO 1111 I = 1,20
00261      DO 1111 J = 1,20
00262      GAIRX(I,J) = GAIRX(I,J) * 0.01
00263      GAIRY(I,J) = GAIRY(I,J) * 0.01
00264 1111 CONTINUE
      C
      C      VALUES BACK.
      C
00265      GO TO 100
00266 205 CONTINUE
      C
      C      WRITE OUT THE SUM TOTALS FOR RESTART
      C
00267      WRITE(3,73) GR01M1, AR01M1, F01M1,TDITI
00268 731  FORMAT(1Y,4F12.4)
00269      CALL SECOND(TSTOP)
00270      TSTOP = TSTOP - TREFIN
00271      CALL STATDOT(TSTOP)
00272      STOP 'END OF ICE MODEL'
00273      END

```

```

TRAN 1.5.1 CYCLE FTV1556 (BUILT 08/03/81) 23 27 SOURCE LISTING
00001 SUBROUTINE ADVECT(UTEC,VICFC,HFFF,DIFF,LAO,HFFM,NX,NY,NX1,NY1)
00002 COMMON /TIME/ DELAYS,FORMS,ADVCTS,BRWTHS,HFATS,HFCHS,INITS
00003 DIMENSION HFFF(28,28,3),VICFC(27,27),VICFC(27,27)
00004      , HFFM(28,28)
00005 COMMON /STEP/ DELTAT, DELTAX, DELTAY, DELTA1, DELTA
00006 CALL SECOND(T1)
00007 NX1 = NX - 1
00008 NY1 = NY - 1
00009 LL = LAO
00010
00011 C NOW DECIDE IF BACKWARD EULER OR LEAPFROG
00012
00013 IF(LL.EQ.1) GO TO 100
00014
00015 C BACKWARD EULER
00016
00017 DELTT=DELTAT
00018 K3=2
00019 K2=2
00020 GO TO 101
00021
00022 C LEAPFROG
00023
00024 100 DELTT=DELTAT*2.0
00025 K3=3
00026 K2=2
00027 101 CONTINUE
00028
00029 C NOW REARRANGE HCS
00030
00031 DO 200 I = 1,24
00032 DO 200 J = 1,24
00033 HFFF(I,1,2)=HFFF(I,J,2)
00034 HFFF(I,1,2)=HFFF(I,J,1)
00035 200 CONTINUE
00036 200 CONTINUE
00037
00038 C NOW GO THROUGH STANDARD CONSERVATIVE ADVECTION
00039
00040 DELTX=DELTAT/(4.0*DELTAY)
00041 DELTY=DELTAT/(4.0*DELTAX)
00042 DO 210 I = 1,24
00043 DO 210 J = 1,24
00044 HFFF(I+1,J+1,1)=HFFF(I+1,J+1,K3)-DELTIX*((HFFF(I+1,J+1,2)+HFFF
* (I+2,J+1,2)) * (VICFC(I+1,J+1) + VICFC(I+1,J)) - (HFFF(I+1,J+1,2)
* + HFFF(I,J+1,2)) * (VICFC(I,J+1) + VICFC(I,J))) - DELTY *
* ((HFFF(I+1,J+1,2) + HFFF(I+1,J+2,2)) * (VICFC(I,J+1) +
* VICFC(I+1,J+1)) - (HFFF(I+1,J+1,2) + HFFF(I+1,J,2)) *
* (VICFC(I,J) + VICFC(I+1,J)))
00045 210 CONTINUE
00046
00047 C NOW DECIDE IF DONE
00048
00049 IF(LL.EQ.2) GO TO 20
00050 IF (LL.EQ.3) GO TO 20
00051 GO TO 102
00052
00053 C CONTINUE
00054
00055 C NOW FIX JP W(T,J,2)
00056 DO 22 I = 1,24
00057 DO 22 J = 1,24

```


TRAM 1.5.1 CYCLE FTN1536 BUILT 04/03/74 23 27 SOURCE LISTING ADVCT

```

00035      HEFF(I,1,2)=HEFF(I,J,3)
00037      CONTINUE
00038      GO TO 102
00039      40 CONTINUE
00040      DO 220 J=1,NY1
00041      DO 220 I=1,NX1
00042      HEFF(I,1,3)=4*HEFF(I,J,2)
00043      HEFF(I,1,2)=0.5*(HEFF(I,J,1)+HEFF(I,J,2))
00044      220 CONTINUE
00045      LL=3
00046      KK=3
00047      GO TO 202
00048      102 CONTINUE
00049      DO 202 J=1,NX1
00050      DO 240 KK=1,2
00051      GO TO (241,242),KK
00052      IF(KK.EQ.1) GO TO 241
00053      IF(KK.EQ.2) GO TO 242
00054      241 CONTINUE
00055      CALL DIFF15(MICE,VICE,HEFF,DIFF1,DELT,HEFFM,NX,NY,NX1,NY1)
00056      GO TO 243
00057      242 CONTINUE
00058      DIFF2=(DELTAX**2)/DELT
00059      CALL DIFF15(MICE,VICE,HEFF,DIFF2,DELT,HEFFM,NX,NY,NX1,NY1)
00060      243 CONTINUE
00061      DO 330 J=1,24
00062      DO 330 I=1,24
00063      HEFF(I,1,1)=(HEFF(I,J,1)+HEFF(I,J,3))*HEFFM(I,J)
00064      330 CONTINUE
00065      CONTINUE
00066      CALL SECOND(T2)
00067      ADVOTS = ADVOTS + (T2 - T1)
00068      RETURN
00069      END

```

NO ERRORS

```

TRAN 1.5.1 CYCLE FTN1554 R11LT 02/03/81 23 27 SOURCE LISTING
00001 SUBROUTINE DIFFUS(JICE,VICE,HEFF,DIFFL,DELT,HEFF4,NX,NY,NY1)
C SPACER
00002 DIMENSION HEFF(24,24,3),VICE(27,27,3),VICE(27,27,3),
* HEFF1(24,24),HEFF4(24,24)
00003 COMMON /DRESS/ DRESS(24,24)
00004 COMMON /STEP/ DELTAT,DELTAX,DELTAY,DELT41,DELT4
C
C SUBROUTINE DIFFUS HEFF, MULTIPLIES BY DELT, AND PUTS RESULTS IN HEFF
C NOT ZERO OUT HEFF1
C
00005 DO 210 I = 1,24
00006 DO 210 J = 1,24
00007 HEFF1(I,J)=0.0
00008 210 CONTINUE
C NOW DO DIFFUSION
00009 DELTXX=DELT*DELT/DELT41/DELT41
00010 DELTYY=DELT*DELT/DELT41/DELT41
00011 DO 220 I = 1,27
00012 DO 220 J = 1,27
00013 HEFF1(I,J)=HEFF(I,J,3)*(HEFF(I+1,J,3)+HEFF(I-1,J,3))+HEFF(I,J,3)*
* -(HEFF(I,J,3)+HEFF(I+1,J,3)+HEFF(I-1,J,3)+HEFF(I,J,3))
* +DELTYY*(HEFF(I,J+1,3)+HEFF(I,J-1,3))+HEFF(I,J,3)*
* -(HEFF(I,J,3)+HEFF(I,J+1,3)+HEFF(I,J-1,3)+HEFF(I,J,3))
00014 220 CONTINUE
00015 DO 240 I = 1,24
00016 DO 240 J = 1,24
00017 HEFF(I,J,3)=HEFF1(I,J)
00018 240 CONTINUE
00019 RETURN
00020 END

```

NO ERRORS

TRAN 1.5.1 CYCLE FTN1564 BUILT 04/03/41 23 27 SOURCE LISTING
00001 SUBROUTINE XSUM(HEFF,S1,NX1,NY1)

C
C PROGRAM SUMS UP VECTOR
C

00002 DIMENSION HEFF(24,24,3)
00003 S1=0.0
00004 DO 100 J = 1,NY1
00005 DO 100 I = 1,NX1
00006 S1 = S1 + HEFF(I,J,1)
00007 100 CONTINUE
00008 RETURN
00009 END

NO ERRORS

ITDAN 1.5.1 CYCLE FTN1556 BUILT 09/03/41 23 27 SOURCE LISTING
00001 SURROUTINE MEAN(HEFF,HMEAN,NX,NY,OUT)

C
C SURROUTINE FINDS MEAN HEFF AT OUTFLOW PTS OF VALUES ABOVE
C

```
00002      DIMENSION HEFF(20,20,3), HMEAN(20,20), OUT(20,20)
00003      DO 101 I=2,NY
00004      DO 101 J=2,NX
00005      HMEAN(I,J)=(HEFF(I+1,J,1)*OUT(I+1,J)+HEFF(I+1,J+1,1)*OUT(I+1,J+1)
* +HEFF(I+1,J-1,1)*OUT(I+1,J-1)+HEFF(I,J+1,1)*OUT(I,J+1)
* +HEFF(I,J-1,1)*OUT(I,J-1)+HEFF(I-1,J,1)*OUT(I-1,J)
* +HEFF(I-1,J+1,1)*OUT(I-1,J+1)+HEFF(I-1,J-1,1)*OUT(I-1,J-1)
*)/(OUT(I+1,J)+OUT(I+1,J+1)+OUT(I+1,J-1)+OUT(I,J+1)+OUT(I,J-1)
* +OUT(I-1,J)+OUT(I-1,J+1)+OUT(I-1,J-1)+.00001)
00006      101 CONTINUE
00007      RETURN
00008      EN
      NO FORCDS
```

```

TRAN 1.5.1 CYCLE FTN1504  RITLT 04/03/41 23 27  SOURCE LISTING
00001      SUBROUTINE DCFAN(GWATX,GWATY,VX,VY,GRD1,GRD2,IVM)
00002      DIMENSION JVV(27,27), WAT(27,27), WATF(27,27)
00003      DIMENSION GWATX(27,27), GWATY(27,27), GRD1(20,20), GRD2(20,20)
00004      COMMON /STPR/ DELTAX, DELTAY, DELTAL, DELTAI, DELTA
00005      DIMENSION W(10,10), WF(10,10)

```

```

00006      DATA ((-F(I,J),I=1,10),J=1,10) /
1      0.0, 0.0, 0.0, 6.0, 11.0, 0.0, 0.0, 0.0, 0.0, 0.0
2      0.0, 0.0, 7.0, 3.0, 4.0, 4.0, 3.0, 0.0, 1.0, 0.0
3      0.0, 7.0, 1.0, 3.0, 4.0, 4.0, 1.0, 4.0, 1.0, 0.0
4      1.0, 4.0, 4.0, 1.0, 3.0, 0.0, 13.0, 4.0, 0.0, 7.0
5      6.0, 7.0, 3.0, 1.0, 1.0, 1.0, 4.0, 0.0, 1.0, 1.0
6      0.0, 4.0, 3.0, 1.0, 1.0, 1.0, 3.0, 0.0, 0.0, 0.0
7      1.0, 6.0, 0.0, 1.0, 1.0, 1.0, 3.0, 0.0, 22.0, 0.0
8      11.0, 4.0, 0.0, 1.0, 1.0, 4.0, 1.0, 0.0, 11.0, 22.0
9      4.0, 7.0, 0.0, 0.0, 3.0, 11.0, 0.0, 0.0, 1.0, 4.0
10     1.0, 11.0, 4.0, 7.0, 11.0, 21.0, 0.0, 0.0, 1.0, 0.0 /

```

```

00007      DO 25 I = 1,27
00008      DO 25 J = 1,27
00009      GWATX(I,J) = 0.0
00010      GWATY(I,J) = 0.0
00011      WAT(I,J) = 0.0
00012      WATF(I,J) = 0.0
00013      25 CONTINUE
00014      DO 7 I = 2,25
00015      READ (7,50) (WAT(I,J),I = 2,25)
00016      7 CONTINUE
00017      50 FORMAT(25F3.0)
00018      RJ = 1.0
00019      DO 15 J = 2,25
00020      RK = 1.0
00021      DO 10 I = 2,25
00022      WAT(I,J) = WAT(I,J) * 10.0
00023      RI = 1.0 + (RK - 1.0) * DELTAL
00024      RI = RI + 0.5
00025      IG = ATN(2I)
00026      RH = RI + 0.5
00027      JG = ATN(2J)
00028      WATF(I,J) = WF(IG,JG) / 100.0
00029      RK = RK + 1
00030      10 CONTINUE
00031      RJ = RJ + DELTAL
00032      RK = RJ + 0.5
00033      JG = ATN(2J)
00034      15 CONTINUE
00035      PRINT 300
00036      300 FORMAT(1X,10WAT AND WATF)
00037      DO 30 J = 1,NV
00038      DO 30 I = 1,NV
00039      X = GRD1(I,J) - 31.0
00040      Y = GRD2(I,J) - 31.0
00041      CALL DCFAN(GWATX(I,J),GWATY(I,J),WAT(I,J),WATF(I,J),X,Y)
00042      30 CONTINUE
00043      RETURN
00044      END

```

40 ERRORS

PLAN 1.5.1 CYCLE FINISH BUILT 03/03/81 23 27 SOURCE LISTING
 00001 SUBROUTINE ENTRY(HFFM,IVV,OUT,VY,VX,VY)

0
 0 SUBROUTINE SETS UP BOUNDARY MASK
 0
 00002 DIMENSION HFFM(23,24), IVV(27,27), OUT(24,24)

0
 0 READ IN VELOCITY MASK
 0

00003 DO 10 I = 1,NY
 00004 READ (7,50) (IVV(I,J),J=1,NX)
 00005 10 CONTINUE
 00006 50 FORMAT(27F2.0)
 00007 DO 20 I = 1,NY
 00008 READ (7,55) (HFFM(I,J),J=1,NX)
 00009 20 CONTINUE
 00010 55 FORMAT(20F2.0)
 00011 DO 30 J = 1,NX
 00012 READ (7,55) (OUT(I,J),I=1,NY)
 00013 30 CONTINUE
 00014 RETURN
 00015 END

00015

```

*TRAN 1.5.1 CYCLE FINISSE BUILT 09/03/81 23 27 SOURCE LISTING
00001 SUBROUTINE RELAX(UICE,VICE,ETA,ZETA,DRASS,DRASSA,AMASS,JVM,
      *THETA,UICE,VICE,HFFEM,NX,NY,NX1,NY1)
00002 DIMENSION UICE(27,27,3), VICE(27,27,3), ETA(24,24)
      *, ZETA(24,24), DRASS(24,24), DRASSA(24,24)
      *, FXETA(4), FYETA(4), UICE(27,27), VICE(27,27)
      *, FYZETA(4), FXZETA(4), AMASS(27,27)
      *, COEF(27,27), FXM(27,27), FYM(27,27)
      *, HFFEM(24,24), JVM(27,27)
      *, FVF(27,27,4), FVF(27,27,4), FY7(27,27,4), FX7(27,27,4)
00003 COMMON /FORCE/ FORCEFX(27,27), FORCEFY(27,27)
00004 COMMON /STEP/ DELTAT, DELTAX, DELTAY, DELTA1, DELTA
00005 COMMON /PRESS/ PRESS(20,24)
00006 COMMON /TIME/ RELAXS, FORAS, ADVCTS, ADVTHS, HEATS, MFSHS, IJITS
00007 CALL SECOND(T1)
00008 TOUT=0
00009 NX1 = NX - 1
00010 NY1 = NY - 1
00011 DEL = 1.7
00012 DELIN = 1.0/DELTAY
00013 DELINP = 0.5/(DELTAX**2)
00014 K=1
      C
      C MUST UPDATE HFF BEFORE CALLING RELAX
      C FIRST SET U(2)=U(1)
      C
00015 DO 40 J=1,NY
00016 DO 40 I=1,NX
      C
      C NOW MAKE SIDE BARY PTS ARE EQUAL TO ZERO
      C
00017 UICE(I, J, 2)=UICE(I, J, 1)
00018 VICE(I, J, 2)=VICE(I, J, 1)
00019 UICE(I, J, 3)=UICE(I, J, 3)*JVM(I, J)
00020 VICE(I, J, 3)=VICE(I, J, 3)*JVM(I, J)
00021 CONTINUE
      C
      C NOW SET UP COEFFICIENTS OF DIAGONAL COMPONENTS
      C
00022 DO 102 I = 2, 24
00023 DO 102 J = 2, 24
00024 C = AMASS(I, J)/DELTAT + 2.0 * THETA * (0.5 * DRASS(I, J)
      * 2.0 * (ETA(I, J)+ETA(I+1, J)+ETA(I, J+1)+ETA(I+1, J+1))
      * 0.5 * (ZETA(I, J)+ZETA(I+1, J)+ZETA(I, J+1)+ZETA(I+1, J+1))
      * )/(4.0*(DELTAX**2))
00025 COEF(I, J) = 1.0/C
00026 102 CONTINUE
      C
      C NOW CALCULATE ALL FUNCTIONS OF PREVIOUS U AND V VALUES
      C
00027 TTHETA=2.0*(1.0-THETA)
00028 DO 111 I=2,NYM1
00029 DO 111 J=2,NXM1
00030 CALL FELLIP(UICE,VICE,ETA,FXETA,I,J,2)
00031 CALL FELLIP(UICE,VICE,ZETA,FXZETA,I,J,2)
00032 CALL FELLIP(VICE,UICE,ETA,FYETA,I,J,2)
00033 CALL FELLIP(VICE,UICE,ZETA,FYZETA,I,J,2)
00034 FX0 = 0.5 * (FXETA(1)+FXZETA(1)+FXETA(2)+FXETA(3)+FXZETA(4)-FXETA(
      * 4))
00035 FX0=TTHETA*FX0
00036 FX1=(AMASS(I, J)/DELTAT-TTHETA*0.5*DRASS(I, J))*UICE(I, J, 2)

```

```

*TRAV 1.5.1 CYCLE FTA1564 0011 04/03/41 23 27 SOURCE LISTING 25LX
00037 FX2=TTHTA*0.5*DPAGS(T,J)*VICE(I,J,2)
00038 FY0 = 1.5 * (FYFTA(1)+FYFTA(2)+FYZFTA(2)+FYZFTA(3)-FYFTA(3) +
*FYFTA(4))
00039 FY0=FY0+TTHTA
00040 FY1=(AMASS(T,J)/DELTA-TTHTA*0.5*DPAGS(T,J)*VICE(I,J,2)
00041 FY2=TTHTA*0.5*DPAGS(T,J)*VICE(I,J,2)
00042 FX0=AMASS(T,J)*0.5*TTHTA*
* (VICE(I,J)*(VICE(I+1,J,2)-VICE(I-1,J,2))
* +VICE(I,J)*(VICE(I,J+1,2)-VICE(I,J-1,2)))/(2.0*DELTA)
00043 FXM(T,J)=FX0+FX1+FX2+FORCEX(T,J)+FX0
00044 FY0=AMASS(T,J)*0.5*TTHTA*
* (VICE(I,J)*(VICE(I+1,J,2)-VICE(I-1,J,2))
* +VICE(I,J)*(VICE(I,J+1,2)-VICE(I,J-1,2)))/(2.0*DELTA)
00045 FYM(T,J)=FY0+FY1+FY2+FORCEY(T,J)+FY0
00046 111 CONTINUE
C
C NO. SET J(3)=J(1)
C
00047 100 CONTINUE
00048 01 101 J=1,NY
00049 01 101 J=1,NX
00050 VICE(I,J,3)=VICE(I,J,1)
00051 VICE(I,J,3)=VICE(I,J,1)
00052 101 CONTINUE
C
C NO. AFTH SPEED
C
00053 CALL FFLD1(VICE,VICE,FTA,FX,1,DELTA)
00054 CALL FFLD1(VICE,VICE,ZFTA,FX,1,DELTA)
00055 CALL FFLD1(VICE,VICE,FTA,FX,1,DELTA)
00056 CALL FFLD1(VICE,VICE,ZFTA,FX,1,DELTA)
00057 01 103 J = 2,25
00058 01 103 J = 2,25
00059 K=1
00060 FXFTA(1) = FX(I,J,1) + DELTA *
*(VICE(I-1,J,K)*(FTA(I,J+1)+FTA(I,J))
+VICE(I,J,2) + DELTA *
*(VICE(I,J-1,K)*(FTA(I,J)+FTA(I+1,J))
+FXFTA(3) = FX(I,J,3) + DELTA * 0.5 *
*(VICE(I-1,J-1,K)*FTA(I,J)+VICE(I,J-1,K) *
*(-FTA(I,J)+FTA(I+1,J))-VICE(I+1,J-1,K)*FTA(I+1,J)
+VICE(I-1,J,K)*(-FTA(I,J+1)+FTA(I,J))
+VICE(I-1,J+1,K)*FTA(I,J+1))
00061 FXFTA(4) = FX(I,J,4) + DELTA * 0.5 *
*(VICE(I-1,J-1,K)*FTA(I,J)+VICE(I,J-1,K) *
*(-FTA(I,J)+FTA(I+1,J))-VICE(I+1,J-1,K)*FTA(I+1,J)
+VICE(I-1,J,K)*(FTA(I,J+1)-FTA(I,J))
+VICE(I-1,J+1,K)*FTA(I,J+1))
00062
00063
00064 FYFTA(1) = FY(I,J,1) + DELTA * (VICE(I-1,J,K)
* (FTA(I,J+1) + FTA(I,J))
00065 FYFTA(2) = FY(I,J,2) + DELTA *
*(VICE(I,J-1,K)*(FTA(I,J)+FTA(I+1,J)))
00066 FYFTA(3) = FY(I,J,3) + 0.5 * DELTA *
*(VICE(I-1,J-1,K)*FTA(I,J)+VICE(I,J-1,K) *
*(-FTA(I,J)+FTA(I+1,J))-VICE(I+1,J-1,K)*FTA(I+1,J)
+VICE(I-1,J,K)*(-FTA(I,J+1)+FTA(I,J))
+VICE(I-1,J+1,K)*FTA(I,J+1))
00067 FYFTA(4) = FY(I,J,4) + 0.5 * DELTA *

```


STRAN 1.5.1 CYCLE FTN1584 ROUTE 04/03/81 22 27 SOURCE LISTING

RELAX

```

      * (HICF(I-1,J-1,K)*ETA(I,J)+HICF(I,J-1,K)*
      * (-ETA(I+1,J)+ETA(I,J))-HICF(I+1,J-1,K)*ETA(I+1,J)
      * +HICF(I-1,J,K)*(ETA(I,J+1)-ETA(I,J))
      * -HICF(I-1,J+1,K)*ETA(I,J+1))
      C
      C
00068      FXZETA(1) = FXZ(I,J,1) + DELTAP *
      * (HICF(I-1,J,K)*(ZETA(I,J+1)+ZETA(I,J)))
00069      FXZETA(4) = FXZ(I,J,4) + DELTAP * 0.5 *
      * (VICF(I-1,J-1,K)*ZETA(I,J)+VICF(I,J-1,K)*
      * (-ZETA(I+1,J)+ZETA(I,J))-VICF(I+1,J-1,K)*ZETA(I+1,J)
      * +VICF(I-1,J,K)*(ZETA(I,J+1)-ZETA(I,J))
      * -VICF(I-1,J+1,K)*ZETA(I,J+1))
      C
      C
00070      FYZETA(2) = FYZ(I,J,2) + DELTAP *
      * (VICF(I,J-1,K)*(ZETA(I,J)+ZETA(I+1,J)))
00071      FYZETA(3) = FYZ(I,J,3) + DELTAP * 0.5 *
      * (HICF(I-1,J-1,K)*ZETA(I,J)+HICF(I,J-1,K)*
      * (-ZETA(I,J)+ZETA(I+1,J))-HICF(I+1,J-1,K)*ZETA(I+1,J)
      * +HICF(I-1,J,K)*(-ZETA(I,J+1)+ZETA(I,J))
      * -HICF(I-1,J+1,K)*ZETA(I,J+1))
      C
      C
00072      FX3 = 0.5 * (FXZETA(1) + FXZETA(1) + FXZETA(2) + FXZETA(3) + FXZETA(4)
      * - FXZETA(4))
00073      FX3=FX3*2.0*THETA
00074      FXCP=AMASS(I,J)*THETA*
      * (HICF(I,J)*(HICF(I+1,J,1)-HICF(I-1,J,1))
      * +VICF(I,J)*(VICF(I,J+1,1)-VICF(I,J-1,1)))*0.5*DELTAP
00075      FX3=FX3+FXCP
00076      FY3 = 0.5 * (FYZETA(1) + FYZETA(2) + FYZETA(2) + FYZETA(3)
      * - FYZETA(3) + FYZETA(4))
00077      FY3=FY3*2.0*THETA
00078      FYCP=AMASS(I,J)*THETA*
      * (HICF(I,J)*(VICF(I+1,J,1)-VICF(I-1,J,1))
      * +VICF(I,J)*(VICF(I,J+1,1)-VICF(I,J-1,1)))*0.5*DELTAP
00079      FY3=FY3+FYCP
00080      FL11=0.5*DRAGA(I,J)*COEFF(I,J)
00081      FL11=FL11*2.0*THETA
00082      F11=(FX4(I,J)+FX3)*COEFF(I,J)
00083      F22=(FY4(I,J)+FY3)*COEFF(I,J)
00084      FL11S=1.0+FL11**2
00085      FL11SI=1.0/FL11S
00086      HICOR=((F11+FL11*F22)*FL11SI)*IVX(I,J)
00087      VICOR=((F22-FL11*F11)*FL11SI)*IVX(I,J)
00088      HICF(I,J,1) = HICF(I,J,1) + WFA*(HICOR-HICF(I,J,1))
00089      VICF(I,J,1) = VICF(I,J,1) + WFA*(VICOR-VICF(I,J,1))
00090      103 CONTINUE
00091      ICOUNT=ICOUNT+1
00092      IF(ICOUNT.GT. 1300) GO TO 201
00093      IF(ICOUNT.GT. 100) WFA = 1.0
      C
      C NOW CHECK MAX ERROR
      C FORM ERROR MATRIX
      C
00094      S1 = 0.0
00095      S2 = 0.0

```

QTRAV 1.5.1 CYCLE FTN1564 R/ILT 24/03/91 23 27 SOURCE LISTING RELAX
 00094 DO 104 J = 1,NY
 00097 DO 104 I = 1,NY
 00099 UERR = UICF(I,J,1) - UICF(I,J,3)
 00100 VERR = VICF(I,J,1) - VICF(I,J,3)
 00101 S1 = AMAX1(ABS(UERR),S1)
 00102 S2 = AMAX1(ABS(VERR),S2)
 00103 104 CONTINUE
 00104 S1 = AMAX1(S1,S2)
 00105 IF(S1.LT.ERROR) GO TO 200
 00106 GO TO 100
 00107 201 CONTINUE
 00108 PRINT 11
 00109 11 FORMAT(1X,NO CONVERGENCE AFTER 400 ITERATIONS)
 00110 C NOW END
 00111 200 CONTINUE
 00112 C PRINT 1.1COUNT
 00113 PRINT 12.51
 00114 PRINT 1.1COUNT
 00115 12 FORMAT(1X,MAX ERROR AND U AND V POWER 1.3F12.5)
 00116 1 FORMAT(1X,NUMBER OF ITERATIONS ARE 1.120)
 00117 CALL SECOND(T2)
 00118 RELAYS = RELAYS + (T2 - T1)
 00119 RETURN
 00120 END
 NO ERRORS

RTN 1.5.1 CYCLE FTM1554 BUILT 08/03/41 22 27 SOURCE LISTING

```

00001      SUBROUTINE FELLIP(JICE,VICE,ETA,F,I,J,K)
      C SPACER
00002      DIMENSION JICE(27,27,3),VICE(27,27,3),ETA(28,28),F(4)
00003      COMMON /STEP/ DELTAY, DELTAX, DELTAY, DELTAY, DELTAY
00004      S1=.5/(DELTAX**2)
00005      F(1)=S1*(JICE(I+1,J,K)*(ETA(I+1,J+1)+ETA(I+1,J))
      *-VICE(I,J,K)*(ETA(I+1,J+1)+ETA(I,J)+ETA(I+1,J)+ETA(I,J+1))
      **VICE(I-1,J,K)*(ETA(I,J+1)+ETA(I,J)))
00006      F(2)=S1*(VICE(I,J+1,K)*(ETA(I+1,J+1)+ETA(I,J+1))
      *-VICE(I,J,K)*(ETA(I+1,J+1)+ETA(I,J)+ETA(I+1,J)+ETA(I,J+1))
      **VICE(I,J-1,K)*(ETA(I,J)+ETA(I+1,J)))
00007      F(3)=S1*(VICE(I-1,J-1,K)*ETA(I,J)+VICE(I,J-1,K)*(-ETA(I,J)
      **ETA(I+1,J))-VICE(I+1,J-1,K)*ETA(I+1,J)+VICE(I-1,J,K)*(-ETA(I,J+1)
      **ETA(I,J)) +VICE(I,J,K)*(-ETA(I,J)-ETA(I+1,J+1)+ETA(I+1,J)
      **ETA(I,J+1)))
00008      F(3)=F(3)+S1*(VICE(I+1,J,K)*(-ETA(I+1,J)+ETA(I+1,J+1))
      *-VICE(I-1,J+1,K)*ETA(I,J+1)
      **VICE(I,J+1,K)*(-ETA(I+1,J+1)+ETA(I,J+1))
      **VICE(I+1,J+1,K)*ETA(I+1,J+1))
00009      F(4)=S1*(VICE(I-1,J-1,K)*ETA(I,J)+VICE(I,J-1,K)*(-ETA(I+1,J)
      **ETA(I,J))-VICE(I+1,J-1,K)*ETA(I+1,J)+VICE(I-1,J,K)*(ETA(I,J+1)
      **ETA(I,J))+VICE(I,J,K)*(ETA(I,J+1)+ETA(I+1,J)-ETA(I,J)-ETA(I+1,
      **J+1)))
00010      F(4)=F(4)+S1*(VICE(I+1,J,K)*(ETA(I+1,J)-ETA(I+1,J+1))
      *-VICE(I-1,J+1,K)*ETA(I,J+1)
      **VICE(I,J+1,K)*(ETA(I+1,J+1)-ETA(I,J+1))
      **VICE(I+1,J+1,K)*ETA(I+1,J+1))
00011      F(4)=F(4)*.5
00012      F(4)=F(4)*.5
00013      RETURN
00014      END
      NO ERRORS

```

```

*PRN 1.5.1 CYCLE FTV1555  BUILT 09/03/41 23 27  SOURCE LISTING
00001      SUBROUTINE AVG(ARRAY,N)
00002      DIMENSION ARRAY(20,20)
00003      NM1 = N - 1
00004      DO 10 I = 1,NM1
00005      DO 10 J = 1,NM1
00006      ARRAY(I,J) = (ARRAY(I,J) + ARRAY(I,J+1) + ARRAY(I+1,J)
*      + ARRAY(I+1,J+1)) / 4.0
00007      10 CONTINUE
00008      RETURN
00009      END
      NO ERRORS

```

```

-TRAN 1.5.1 CYCLE FINISH: 04/03/41 03 27 SOURCE LISTING
00001 SUBROUTINE HEAT(200,600,HEFF,AV20,FS,F4FF,PS,TAIR,TAIR,
* ITR,NT,NT,NT,NUMBER)
00002 CHARACTER TAIR,ITR
00003 COMMON /TIME/ RELAYS,FSH,FS,ACTS,TAIR,TAIR,TAIR,TAIR
00004 DIMENSION /200/ FSH(20,20)
00005 DIMENSION TICE(20,20), TITX(20,20), TAT(20,20), TA(20,20),
* FLO(20,20), GWT(20,20), GWTJ(20,20), GWTJ(20,20),
* GWTJ(20,20), PS(20,20), FS(20,20), F4FF(20,20),
* FJ(20,20), APS(20,20,3), HEFF(20,20,3), ITR(3)
* IS(20,20)
00006 CALL SECOND(TI)
C
C
00007 DO 10 I = 1,NT
00008 DO 10 J = 1,NT
C
C
00009 ITR(I,J) = S-T(GWT(I,J) * 8 * 2 + GWT(I,J) * 8 * 2)
00010 DO ITRIF
00011 CALL INITIAL(4,TAIR,200,I,200,ITR,NUMBER,0)
00012 CALL AVG(TAIR,1,400)
C
C
00013 DO 15 I = 1,20
00014 DO 15 J = 1,20
00015 TAIR(I,J) = TAIR(I,J) + 273.0
00016 CONTINUE
00017 CALL INITIAL(5,PS,200,I,200,ITR,NUMBER,0)
00018 CALL AVG(PS,NUMBER)
00019 CALL INITIAL(6,FS,200,I,200,ITR,NUMBER,0)
00020 CALL AVG(FS,NUMBER)
00021 DO 20 J = 1,20
00022 DO 20 I = 1,20
00023 PS(I,J) = (0.22 * FS(I,J)) / (PS(I,J) + FS(I,J))
00024 CONTINUE
00025 CALL INITIAL(5,FSH,200,I,200,ITR,NUMBER,0)
00026 CALL AVG(FSH,NUMBER)
00027 CALL INITIAL(7,PS,200,I,200,ITR,NUMBER,0)
00028 CALL AVG(PS,NUMBER)
00029 CALL INITIAL(8,FS,200,I,200,ITR,NUMBER,0)
00030 CALL AVG(FS,NUMBER)
00031 RINV = 1.75
00032 DO 30 J = 1,20
00033 DO 30 I = 1,20
00034 PS(I,J) = PS(I,J) * RINV
00035 FS(I,J) = FS(I,J) * RINV
00036 FSH(I,J) = FSH(I,J) * RINV
00037 FLO(I,J) = PS(I,J) + FS(I,J) + FSH(I,J)
00038 CONTINUE
C
C
00039 HXIX = 1.0 / 30.0
00040 DO 200 J = 1,20
00041 DO 200 I = 1,20
00042 AREA(I,J) = MAX(0.15,AREA(I,J))
00043 CONTINUE
00044 DO 201 J = 1,20
00045 DO 201 I = 1,20

```

PROGRAM 1.5.1 CYCLE FURNACE BUILT 04/03/81 23 27 SOURCE LISTING HEAT 0

```
00046      TMIX(I,1) = 271.2
00047      TICE(I,1) = 273.0
00048      201 CONTINUE
00049      KOPEN = -1
00050      CALL RIDGET(HEFF,FI,KOPEN,NX1,NY1,JS,TICE,TMIX,TATR,QA,FLO)
00051      KOPEN = 2
00052      CALL RIDGET(HEFF,HEFF,KOPEN,NX1,NY1,JS,TICE,TMIX,TATR,QA,FLO)
00053      1) 1047 T = 2,NY1
00054      00 1047 T = 2,NY1
00055      HEFF(I,1) = HEFF(I,1) * AREA(I,1,2) + (1.0 - AREA(I,1,2)) * FC(I
      * J)
00056      1047 CONTINUE
00057      CALL SECOND(T2)
00058      HEATS = HEATS + (T2 - T1)
00059      RETURN
00060      END
```

NO ERRORS

```

*TRAV 1.5.1 CYCLE FIVE66  BUILD 04/03/91 23 27  SOURCE LISTING
000001      SUBROUTINE SUBSET(HEFF,FICE,KOPEN,NXI,NYI,UG,TICE,TMIX,TATP,
*           DA,FLD)
000002      DIMENSION TICE(24,24), HEFF(24,24,3), FICE(24,24), TMIX(24,24),
*           TATP(24,24), DA(24,24), FLD(24,24), UG(24,24)
000003      COMMON /PAB/ FSH(24,24)
000004      QS1 = 1.422/1013.0
000005      C1=2.773420E-4
000006      C2=-2.5013324E-03
000007      C3=0.37220844
000008      C4=-134.43774
000009      C5=4553.1025
000010      C6=1.3E-15/302.0
000011      FA=-2.0
000012      T4=271.2
000013      TMAY=3
000014      T1=2.24E
000015      T1X = 5.4475E+03
000016      T1I = 5.4475E+03
000017      T3 = 5.5E-08
000018      TMFLT=272.14
000019      T4FLTP=273.15
000020      IF(KOPEN.GT.0) GO TO 51
000021      PRINT 1000
000022      1000  FORMAT(1X,'COMPUTING THIN ICE GROWTH RATE')
000023      DO 101 J = 1,24
000024      DO 101 I = 1,24
000025      ALP = 0.1
000026      A1 = 1.0 * FSH(I,J) + FLD(I,J) + T1 * UG(I,J) * TATP(I,J) +
*           T1I * IG(I,J) * DA(I,J)
000027      R = QS1 * 5.11 * EXP(17.2-46 * (T4IX(I,J) - T4FLT) /
*           (TMIX(I,J) - TMFLT + 237.3))
000028      A2 = -T1 * UG(I,J) * TICE(I,J) - T1I * IG(I,J) * R - T3 *
*           (TICE(I,J) * * 4)
000029      FICE(I,J) = 0.0 * (FA - A1 - A2)
000030      101  CONTINUE
000031      RETURN
000032      51  CONTINUE
000033      PRINT 1005
000034      1005  FORMAT(1X,'COMPUTING THICK ICE GROWTH RATE')
000035      IFP = 0
000036      60  CONTINUE
000037      DO 104 J = 1,24
000038      DO 104 I = 1,24
000039      HEFF(I,J,2) = AMAX1(HEFF(I,J,2),0.05)
000040      104  CONTINUE
000041      DO 105 J = 1,24
000042      DO 105 I = 1,24
000043      ALP = 0.75
000044      IF(TICE(I,J).GT. TMFLTP) ALP = 0.514
000045      A1 = (1.0 - ALP) * FSH(I,J) + FLD(I,J) + T1 * UG(I,J) * TATP(I,J)
*           + T1I * IG(I,J) * DA(I,J)
000046      R = QS1 * (C1 * TICE(I,J) * * 4 + C2 * TICE(I,J) * * 3 + C3 *
*           TICE(I,J) * * 2 + C4 * TICE(I,J) + C5)
000047      A2 = -T1 * UG(I,J) * TICE(I,J) - T1I * IG(I,J) * R - T3 *
*           (TICE(I,J) * * 4)
000048      R = 2.1455 / HEFF(I,J,2)
000049      A3 = 4.0 * C3 * (TICE(I,J) * * 3) + R + T1 * UG(I,J)
000050      R = R * (T3 - TICE(I,J))
000051      TICE(I,J) = TICE(I,J) + (A1 + A2 + R) / A3
000052      FICE(I,J) = 0.0 * (FA - A1 - A2)

```

TRAN 1.5.1 CYCLE FINISHES BUILD 04/03/41 23 27 SOURCE LISTING

3106-1

```
00053      105 CONTINUE
00054          ITER=ITER+1
00055          DO 107 I=1,NY1
00056          DO 107 J=1,NX1
00057          TICE(I,J)=AMIN1(TICE(I,J),INFLT)
00058      107 CONTINUE
00059      IF(ITER.GT. IMAX) GO TO 52
00060      GO TO 50
00061      52 CONTINUE
00062      RETURN
00063      END
```

NO ERRORS

TRAN 1.5.1 CYCLE ETN1556 4/11/71 23 27 SOURCE LISTING F02

```

C
00028     FORCEX(I,J) = FORCEX(I,J) + DPHATN(I,J) * (COSPHAT * GWATX(I,J) -
      * SINPHAT * GWATY(I,J))
00029     FORCEY(I,J) = FORCEY(I,J) + DPHATN(I,J) * (SINPHAT * GWATX(I,J)
      * +COSPHAT * GWATY(I,J))
00030     107 CONTINUE
C
C     NOW AT IN TILT
C
00031     DO 109 I = 1,27
00032     DO 109 J = 1,27
00033     FORCEX(I,J) = FORCEX(I,J) - CIP(I,J) * GWATY(I,J)
00034     FORCEY(I,J) = FORCEY(I,J) + CIP(I,J) * GWATX(I,J)
00035     109 CONTINUE
C
C     STOP THE INPUT DATA
C
C     NOW SET UP THE PRESSURE AND VISCOSITIES
C     FIRST SET UP CONSTANTS
C     5.747E-10 IS 0.1 PER CENT PER DAY STRAIN RATE
C     NOW SET UP VALUES
00036     DO 115 J = 1,27
00037     DO 115 I = 1,27
00038     PRESS(I,J) = 5.747E-10 * HREF(I,J,1) * EXP(-20.0 * (1.0
      * - HREF(I,J,1)))
00039     115 CONTINUE
00040     1000 CONTINUE
00041     CALL PLAST(HREF,VISC,PRESS,ETA,ZETA,ECCEN,
      * HREFX,NX,NY,NTM)
C     NOW SET VISCOSITIES AND PRESSURE EQUAL TO ZERO AT OUTSIDE PTS
00042     DO 106 I=1,NX
00043     DO 106 J=1,NY
00044     ETA(I,J)=ETA(I,J)*OUT(I,J)
00045     ZETA(I,J)=ZETA(I,J)*OUT(I,J)
00046     106 CONTINUE
C     NOW CALCULATE PRESSURE FORCE AND ADD TO EXTERNAL FORCE
00047     DO 117 J = 1,27
00048     DO 117 I = 1,27
00049     FORCEX(I,J)=FORCEX(I,J)-(0.25/DELTA T)*
      * ((PRESS(I+1,J) * OUT(I+1,J)) + (PRESS(I+1,J+1) * OUT(I+1,J+1))
      * - (PRESS(I,J) * OUT(I,J)) - (PRESS(I,J+1) * OUT(I,J+1)))
00050     FORCEY(I,J)=FORCEY(I,J)-(0.25/DELTA T)*
      * ((PRESS(I,J+1) * OUT(I,J+1)) + (PRESS(I+1,J+1) * OUT(I+1,J+1))
      * - (PRESS(I,J) * OUT(I,J)) - (PRESS(I+1,J) * OUT(I+1,J)))
C     NOW PUT IN MINIMAL MASS FOR TIME STEPPING CALCULATIONS
00051     117 CONTINUE
00052     CALL SECOND(T2)
00053     FORMS = FORMS + (T2 - T1)
00054     RETURN
00055     END
NO ERRORS

```

```

TRAN 1.5.1 CYCLE FINISHED 4/11/77 22 27 SOURCE LISTING
00001 SUBROUTINE FORM (ITCF,VICF,ETA,ZETA,AMASS,GAIRX,GAIRY,GAIV,
*   GARRS,GARRA,GJIT,HEFF,XY,XY,XZ,XY,XY,HEFF,AREF)
C
C ***** BASIC INPUT PARAMETERS FOR RELAXATION *****
C
00002 DIMENSION ITCF(27,27,3),VICF(27,27,3),ETA(24,24),ZETA(24,24)
*   AMASS(27,27),GAIRX(24,24),GAIRY(24,24),GAIV(27,27),
*   GARRS(24,24,3),GARRA(24,24,3),GJIT(24,24),
00003 DIMENSION GARRS(24,24),GARRA(24,24),HEFF(24,24),
*   GJIT(24,24),HEFF(24,24,3),GARRS(27,27),
*   GARRA(27,27)
00004 COMMON /TIME/ DELAYS,FORIS,ANVTS,SP,TAS,HEATS,AFSHS,IVITS
00005 COMMON /CONST/ CONSTX(27,27),CONSTY(27,27)
00006 COMMON /CONST/ CONSTS(24,24)
00007 COMMON /STEP/ DELTAT,DELTAX,DELTAY,DELTAT,DELTAT
00008 DATA CONSTX/1.45E-04/
*   CONSTY/1.45E-04/
*   CONSTS/1.45E-04/
*   CONSTS/1.45E-04/
*   CONSTS/1.45E-04/
*   CONSTS/1.45E-04/
*   CONSTS/2.0/
00009 CALL SECONDS(TI)
C
C ***** SET UP CONSTANTS TERM *****
C
00010 DO 101 I = 1,27
00011 DO 101 J = 1,27
00012 AMASS(I,J) = 0.01E+03 * 0.25 * (HEFF(I,J,1) + HEFF(I+1,J,1) +
*   HEFF(I,J+1,1) + HEFF(I+1,J+1,1))
00013 COM(I,J) = AMASS(I,J) * 5000
00014 DEATM(I,J) = 5.0 * SQRT((ITCF(I,J,1) - GAIRX(I,J)) ** 2 +
*   (VICF(I,J,1) - GAIRY(I,J)) ** 2)
00015 GARRS(I,J) = DEATM(I,J) * SIN(T) + COS(I,J)
00016 IF 1 CONTINUE
C
C ***** SET UP SYMMETRIC TERM *****
C
00017 DO 105 I = 1,27
00018 JJ = J + 1
00019 DO 105 J = 1,27
00020 II = I + 1
00021 GAIRX = GARRS(I,J) * 0.01E+03 * SQRT(GAIRX(II,JJ) ** 2 +
*   GAIRY(II,JJ) ** 2)
C
C ***** SET UP SYMMETRIC TERM *****
C
00022 GARRS(I,J) = GAIRX(I,J) * COS(T)
C
C ***** NOW SET UP FORCING FIELD *****
C ***** FIRST THE TEND *****
00023 FORCEX(I,J) = GARRS * (COS(T) * GAIRX(II,JJ) -
*   SIN(T) * GAIRY(II,JJ))
00024 FORCEY(I,J) = GARRS * (SIN(T) * GAIRX(II,JJ) +
*   COS(T) * GAIRY(II,JJ))
C
00025 IF 1 CONTINUE
00026 DO 107 I = 1,27
00027 DO 107 J = 1,27
C ***** AND THE CURRENT FORCE *****

```

```

TRAN 1.5.1 CYCLE ETN1556 01/03/81 23 27 SOURCE LISTING
00001 SUBROUTINE PLAST(JICE,VICE,PRESS,ETA,ZETA,FCFV,HFFV,
* NYI,NYI,DIV)
C SUBROUTINE CALCULATES STRAIN RATES AND VISCOSIS PARAMETERS
00002 DIMENSION JICE(27,27,3),VICE(27,27,3),PRESS(27,27)
* ZETA(27,27),DIV(27,27)
* STRESS(27,27,3),ETA(27,27)
* HFFV(27,27)
00003 DIMENSION F11(27,27),F22(27,27),E12(27,27)
00004 COMMON /STEP/ DELTAT,DELTAY,DELTAX,DELTAT,DELTAT
00005 FCM2=1.0/(FCFV**2)
00006 GAM=1.0E-20
C NOW EVALUATE STRAIN RATES
C
C IF COLUMNED FIND F11(I,J),F12(I,J),F22(I,J) UNTIL NO.
C THEREFORE WE ASSIGN THEM EQUAL ZERO. THEY ARE COMPUTED
C FROM VELOCITY AT THE JOINTS *** THANUS ***
C
00007 F11 = 0.0
00008 F12 = 0.0
00009 F22 = 0.0
00010 ZAIN = 4.0E+04
C***
00011 DO 101 J = 1,27
00012 DO 101 I = 1,27
00013 F11(I,J) = (0.5/DELTAX) * (JICE(I,J,1) + JICE(I,J-1,1)
* -JICE(I-1,J,1) - JICE(I-1,J-1,1))
00014 F22(I,J) = (0.5/DELTAY) * (VICE(I,J,1) + VICE(I-1,J,1)
* -VICE(I,J-1,1) - VICE(I-1,J-1,1))
00015 F12(I,J) = (0.25/DELTAX) * (JICE(I,J,1) + JICE(I-1,J,1)
* -JICE(I,J-1,1) - JICE(I-1,J-1,1))
* + (0.25/DELTAY) * (VICE(I,J,1) + VICE(I,J-1,1)
* -VICE(I-1,J,1) - VICE(I-1,J-1,1))
00016 101 CONTINUE
C NOW EVALUATE VISCOSITIES
C
00017 DO 110 J = 1,27
00018 DO 110 I = 1,27
00019 DELT = (F11(I,J) ** 2 + F22(I,J) ** 2) * (1.0 + FCM2) + 4.0 *
* FCM2 * F12(I,J) ** 2 + 2.0 * F11(I,J) * F22(I,J) *
* (1.0 - FCM2)
00020 DELT=SQRT(DELT)
00021 DELT=MAX(1.0E-10,DELT)
00022 ZETA(I,J)=0.5*PRESS(I,J)/DELT
C NOW PUT MIN AND MAX VISCOSITIES IN
00023 110 CONTINUE
00024 ZAIN = 4.0E+04
00025 DO 115 J = 1,27
00026 DO 115 I = 1,27
00027 ZMAX = (5.0E+12 / 2.0E+04) * PRESS(I,J)
00028 ZETA(I,J) = AMIN(ZMAX,ZETA(I,J))
00029 ZETA(I,J) = AMAX(ZMIN,ZETA(I,J))
00030 115 CONTINUE
00031 DO 120 J = 1,27
00032 DO 120 I = 1,27
00033 ETA(I,J)=FCM2*ZETA(I,J)
00034 F11(I,J) = F11(I,J) * HFFV(I,J)
00035 F22(I,J) = F22(I,J) * HFFV(I,J)
00036 F12(I,J) = F12(I,J) * HFFV(I,J)
00037 SS11 = (ZETA(I,J) - ETA(I,J)) * (F11(I,J) + F22(I,J)) - PRESS(I
* * 0.5

```

```

TRAN 1.5.1 CYCLE FTNIR35 0011 02/03/91 23 27 SOURCE LISTING 2.151
00038 STRESS(I,J,1) = (2.0 * FTA(I,J) * F11(I,J) + SS11)
00039 STRESS(I,J,2) = 2.0 * FTA(I,J) * E22(I,J) + SS11
00040 STRESS(I,J,3) = 2.0 * FTA(I,J) * F12(I,J)
      C
      C CALCULATE THE ICE DIVERGENCE IS THE SUM OF THE STRAIN RATES
      C
00041 DIV(I,J) = F11(I,J) + E22(I,J)
00042 120 CONTINUE
00043 GET IDV
00044 END
NO ERROR

```

```

TRAN 1.5.1 CYCLE FTN1554 3 JULY 68/03/51 22 27 SOURCE LISTING
00001 SUBROUTINE ADJUST(HEFF,AREA,OUT,HEFFM,VX,VY,NX(NV))
00002 DIMENSION HEFF(24,24,1),AREA(24,24,3)
00003 DIMENSION HEFFM(24,24),OUT(24,24)
00004 DIMENSION OUT2(24,24)
00005 CALL MEAN(HEFF,OUT2,VX,VY,OUT)
00006 DO 100 J = 2,27
00007 DO 100 I = 2,27
00008 HEFF(I,J,1) = HEFF(I,J,1) + (HEFFM(I,J) - OUT(I,J)) * OUT2(I,J)
00009 100 CONTINUE
00010 CALL MEAN(HEFF,OUT2,VX,VY,OUT)
00011 DO 110 J = 2,27
00012 DO 110 I = 2,27
00013 AREA(I,J,1) = AREA(I,J,1) + (HEFFM(I,J) - OUT(I,J)) * OUT2(I,J)
00014 110 CONTINUE
00015 RETURN
00016 END
V) F220-S

```

TRAN 1.5.1 CYCLE FINISHED BUILD 0-703731 23 27 SOURCE LISTING
00001 SUBROUTINE MESH(IGRI,IGRIJ,IX,IXI,MYI,MYI)

```

00002 SUBROUTINE MESH
00003
00004 PURPOSE TO CALCULATE THE FOUR I,J GRID POINTS FOR THE MODEL
00005 GRID AND CALCULATE THE MESH SIZE.
00006
00007 USAGE
00008
00009     IGRIT      DEFI      IO,II      DEFINING I GRID POINTS
00010             DEFI      JO,JI      DEFINING J GRID POINTS
00011
00012     IO,II,JO,JI DEFINED AS FOLLOWS
00013
00014             X             X
00015             (I, I)             (II, II)
00016
00017             X             X
00018             (IO, IO)             (JI, JI)
00019
00020             M             NUMBER OF GRID POINTS ON A SIDE
00021
00022     OUTPUT
00023             IGRI,IGRIJ      I,J GRID POINTS FOR THE MODEL
00024                             GRID
00025             DELTA          MESH SIZE
00026
00027 METHOD
00028     THE DEFINING GRID POINTS ARE READ FROM THE INPUT STREAM.
00029     THESE VALUES ARE USED TO CALCULATE THE I,J POINTS OF THE MODEL
00030     GRID. THE MAP FACTOR IS CALCULATED AT EACH POINT AND THE AVERAGE
00031     MAP FACTOR IS USED TO CALCULATE THE MESH SIZE OF THE GRID.
00032
00033
00034 IMPLICIT REAL (A-Z)
00035 COMMON /X/IXI,MYI(20), IXI(20), MYI(20)
00036 COMMON /TIME/ DELTA,DELTA,DELTA,DELTA,DELTA,DELTA,DELTA,DELTA,DELTA,DELTA
00037 DIMENSION IGRIT(20,20), IGRJ(20,20)
00038 COMMON /MESH/ DELTA,DELTA,DELTA,DELTA,DELTA,DELTA,DELTA,DELTA,DELTA,DELTA
00039 INTERGER I,J,IX,IXI,MYI,MYI
00040 INTERGER I,II
00041 CALL SECOND(MESH)
00042
00043 READ DEFINING POINTS
00044
00045 READ (7,10) IO,II
00046 READ (7,10) JO,JI
00047 READ (7,10) M
00048
00049 12  FORMAT(13)
00050 10  FORMAT(2F10.2)
00051 PRINT 1000, IO,II,JO,JI
00052 1000 FORMAT(1X,DEFINING GRID POINTS: /1X,IO AND II 1.215,
00053           * /1X,JO AND JI 1.215)
00054
00055 MX = M - 2
00056 MY = M - 2
00057 MXI = M - 1
00058 MYI = M - 1

```

```

TRAN 1.5.1 CYCLE FINISHS  PRINT 04/03/81 23 27  SOURCE LISTING  MESH
C
C      SET GRID INCREMENTS
C
C      SET UP J POINTS
C
00021      DELTA1 = (J1 - J0) / FLOAT(N-1)
00022      RI = J1
00023      DO 15 I = 1,N
00024      DO 13 J = 1,M
00025      GRID(I,J) = RI
00026      13 CONTINUE
00027      RI = RI + DELTA1
00028      15 CONTINUE
C
C
C      SET UP I MESH
C
00029      DELTA = (I1 - I0) / FLOAT(N-1)
00030      RJ = I0
00031      DO 25 I = 1,N
00032      DO 23 J = 1,M
00033      GRID(I,J) = RJ
00034      23 CONTINUE
00035      RJ = RJ + DELTA
00036      25 CONTINUE
C
C
00037      DELTA = (DELTA + DELTA1) * 0.5
C
C      COMPUTE THE MESH SIZE
C
00038      SUM = 0.0
00039      DO 100 I = 1,N
00040      DO 100 J = 1,M
00041      DSD = ((GRID(I,J) - 31.0) * * 2) + ((GRID(I,J) - 31.0) * * 2
00042      STNL = (1341.4224 - DSD) / (1341.4224 + DSD)
00043      XMAP = 1.4460254032 / (1 + STNL)
00044      SUM = SUM + XMAP
00045      100 CONTINUE
00046      XMAP2 = SUM / (N * M)
00047      DELTAX = DELTA * 381000.0 * XMAP2
00048      DELTAX = ATN(DELTA)
00049      DELTAY = DELTAX
00050      PRINT 1005,XMAP2,DELTAX
00051      1005 FORMAT(1X,FAVE2435 MAP FACTOR IS 1.5F10.3,
C
C      * 1X,1THE MESH SIZE IS (IN METERS) 1.5F10.3)
C
C      COMPUTE LOCAL GRID POINTS OF RUDYS
C
C
00052      N = 1.0 / DELTA
00053      RI = 1.0 / DELTA1
00054      DO 135 L = 1,20
00055      I1 = 317YI(L) - I0
00056      J1 = 317YJ(L) - J0
00057      RX(L) = I1 * N
00058      RY(L) = J1 * N
00059      135 CONTINUE
00060      PRINT 77
00061      PRINT 77,(RX(LL),LL=1,20)
00062      77 FORMAT(140.0LOCAL RUDY GRID POINTS 1/1X,20F4.1)

```

TRAN 1.5.1 CYCLE FTW1535 31JLT 04/03/41 23 27 SOURCE LISTING

VFSH

00053 PRINT 75.(BY(LL).LL=1.20)
00054 74 FORMAT(140.0 Y POINTS 1/1X.20F4.1)
00055 RETURN
00056 END
NO ERRORS

[illegible]

```

TRAN 1.5.1 CYCLE FTIME34  BUILD 09/03/71 23 27  SOURCE LISTING
00001      SUBROUTINE INITIAL_(N0,GRIP,GR01,GR21,IT3,N,IT40)
00002      DIMENSION GR01(24,22), GR0J(2),GR2, GR12(24,24), LABEL(2),
      *      IP00(4)
00003      COMMON /TIME/ DELAYS,FOCUS,ADVCTS,GRPHS,FEATS,MESHS,INITS
00004      LOGICAL IP(4), MASK1,MASK2,IOL,ITL
00005      LOGICAL MASK3,MASK4
00006      COMMON /HFFFF/ IDENT(24), DATA(3,53), FILL(107)
00007      CHARACTER*8 IFILE,IT,ITL,ITG(3),LAFIL,IP0
00008      EQUIVALENCE (IT,ITL), (IP,IP0), (IOL,IDENT(1))
00009      DATA IDENT(4) /44 3243/
00010      DATA IDENT(3) /44 3233/
00011      DATA MASK1 /XXXXXXXXXXXXXXXXXXXX/
      *      MASK2 /XXXXXXXXXX0000000000/
      *      MASK3 /XXXXXXXXXX0000000000/
      *      MASK4 /XXXXXXXXXX0000000000/
      *      (IP00(KK),KK=1,4) /3H420, 3H421, 3H410, 3H411, 3H412,
      *      3H411, 3H414, 3H415/
00012      IFILE = 'HT4000'
00013      CALL SECND(T1)
00014      CALL HTIME50(IT3,IT)
00015      ITL = ITL .AND. MASK3
00016      ITL = ITL .OR. MASK4
00017      IOL = IP(N0) .AND. MASK1
00018      IOL = IOL .OR. MASK2
00019      IOL = IOL .OR. ITL
00020      IDENT(2) = ITG(1)
00021      LABEL(2) = IDENT(2)
00022      LABEL(1) = IDENT(1)
00023      PRINT 600,LABEL(1),LABEL(2)
00024      600 FORMAT(1X,'INITIAL_  READING RECORD 1,243)
00025      CALL CHECKNO(IFILE,LABEL,3943,LE0,IS)
00026      IF (IS .EQ. 0) STOP 'CHECKNO NO DATA INITIAL_'
00027      CALL CREADER(IFILE,LABEL,IDENT,3943,LE0,IS)
00028      DO 200 I = 1,N
00029      DO 200 J = 1,N
00030      CALL TUTOR(DATA,53,53,GR0J(I,J),GR01(I,J),GRIP(I,J))
00031      200 CONTINUE
00032      DO 500 I = 27,35
00033      PRINT 75,(DATA(I,J),I=26,35)
00034      500 CONTINUE
00035      75 FORMAT(1X,1F10,4)
00036      CALL SECND(T2)
00037      INITS = INITS + (T2 - T1)
00038      RETURN
00039      END
      *  END OF TRAN 1.5.1

```

STPAM 1.5.1 CYCLE STRESS BUILT 04/03/81 23 27 SOURCE LISTING
 00001 SURROUTINE HAPLOT(HEFF,ARFA,ITG,ITAU,GRJ,GRD,IX,XY)

CCC

SURROUTINE HAPLOT

PURPOSE TO FORMAT THE THICKNESS AND COMPACTNESS FOR PRINTED AND
 PLOTTED OUTPUT.

USAGE

INPUT

HEFF	ICE THICKNESS
ARFA	ICE COMPACTNESS
PRESS	ICE PRESSURE OR ICE STRENGTH
ITG	DATE TIME GRID
GRJ,GRD	I, J, POINTS
IX,XY	GRID DIMENSIONS

COMMON BLOCKS

/PLOT/, /DREF/, /DATAI/, /ZRAW/

EXTERNALS

DAY, EXTRAP, IDENTG, TABLE, ZFILE, ZRFILE, ZFILE

METHOD

THE THICKNESS VALUES ARE CONVERTED TO CM AND ARE WRITTEN
 TO THE ZRAWING DATA FILE. THE COMPACTNESS VALUES ARE WRITTEN TO
 THE ZRAWING FILE ALSO. THE OLD RECORDS ARE DELETED. BOTH OF THE
 ARRAYS ARE SENT TO TABLE FOR PRINTED OUTPUT.

THE PLOT FILES ARE PREPARED BY FIRST SETTING UP THE 20
 WORD IDENTIFICATION BLOCK NECESSARY FOR EVOC DATA RECORDS.
 THE DATA VALUES ARE THEN PUT IN TERMS OF THE 63 - 63 GRID
 AND WRITTEN TO THE ZRAWING DATA FILE FOR PLOTTING.

CCC

00002 COMMON /DP/ ITA(24), ARRAY(425), FL(375)
 00003 COMMON /PRESS/ PRESS(24,24)
 00004 DIMENSION HEFF(24,24,3), ARFA(24,24,3)
 00005 DIMENSION GRJ(24,24), GRD(24,24)
 00006 DIMENSION ITG(3), IRD(3)
 00007 CHARACTER*8 ITA, ITG, IT, LABEL(2)
 00008 CHARACTER*8 ITG
 00009 CHARACTER*8 ITI, ITJ
 00010 DATA ITA/ZATHK+ 24/

*. ITA(3) /RH 549/
 *. ITI /HOCRY+ 24/
 *. ITJ /HOCRY+ 24/
 *. ITG(4) /HFD54901Y/

00011 ITA(2) = ITG(1)
 00012 CALL PRINASC(ITA,IT)

C
 C
 C

WRITE OUT THE THICKNESS AND COMPACTNESS DATA FIELDS

00013 K = 0
 00014 NY = NY - 1
 00015 NY = NY - 1
 00016 DO 10 I = 2, NYX
 00017 DO 10 J = 2, NY
 00018 K = K + 1
 00019 ARRAY(K) = HEFF(I,J,1) * 100.0
 00020 10 CONTINUE
 00021 IFILE = ZHASEVNC

PTRAN 1.5.1 CYCLE STIMULUS (JULY 08/03/4) 23 27 SOURCE LISTING
 INVERSE . X AND Y MUST BE EXPRESSED IN GRID DISTANCE
 FROM THE POLE . /

IMPLICIT C

```

00010 CALL INDEF (ARRAYX(I,J),ARRAYY(I,J),D(K),FF(K),X,Y)
00020
00030 CONVERT ICE MOVEMENT FROM METERS/SEC. TO KNOTS
00040
00050 FF(K) = (FF(K) / 0.5144) * 100.0
00060 100 CONTINUE
00070 IFILE = 74455000
00080 LABEL(1) = I(1)
00090 LABEL(2) = I(2)
00100 CALL CRTITER(IFILE,LABEL,I,440,ISTAT)
00110 IF(ISTAT.NE.0) GO TO 1000
00120 IF(2) = I(2)
00130 LABEL(1) = IF(1)
00140 CALL CRTITER(IFILE,LABEL,IF,440,ISTAT)
00150 IF(ISTAT.NE.0) GO TO 1000
00160 RETURN
00170 1000 PRINT 1010,ISTAT,LABEL(1)
00180 1010 FORMAT(1X,ISTAT IS 1,IF,1 OF WRITE OF 1,00)
00190 STOP AND WRITE IN JOURNAL
00200 END
  
```

END

IPAV 1.5.1 CYCLE FYN1564 BUILT 09/03/41 23 27 SOURCE LISTING
 00001 SUBROUTINE HVPL0T(ARRAYX,ARRAYY,ITG,NX,NY,GRID,
 GRID,ITAU)

000

SUBROUTINE HVPL0T

PURPOSE TO OUTPUT THE DIRECTION,SPEED VECTORS OF ICE DRIFT
 FOR PRINTED AND PLOTTED OUTPUT.

USAGE

INPUT	ARRAYX	ARRAY OF U ICE DRIFT COMPONENT
	ARRAYY	ARRAY OF V ICE DRIFT COMPONENT
	ITG	DATE TIME GROUP
	NX,NY	GRID DIMENSIONS
	ITAU	FORECAST TAU VALUE

COMMON BLOCKS

/PLOT/, /DIFF/, /TRANS/

EXTERNALS

DAY, TABLE, INDIFF, ZDELFI, ZDRIFT

METHOD

THE U,V COMPONENTS ARE CONVERTED TO A METEOROLOGICAL
 DIRECTION AND SPEED FOR THE I,J GRID. THE SPEED IS CONVERTED TO
 KNOTS AND MULTIPLIED BY 100. THESE VALUES(DIRECTION AND FORCE)
 ARE WRITTEN TO THE ZRANDIO FILE AND THE OLDER RECORDS ARE DELETED.
 THE DIRECTION AND FORCE ARE THEN PACKED INTO ONE WORD,
 TOGETHER WITH THE RESPECTIVE I,J GRID VALUE. THIS RECORD IS THEN
 WRITTEN TO THE ZRANDIO DATA BASE.
 SUBROUTINE TABLE IS CALLED TO FORMAT THE DIRECTION AND
 FORCE FOR PRINTED OUTPUT.

000

00002
 00003
 00004
 00005
 00006

COMMON /PLOT/ I(24),J(24),FILL(375)
 COMMON /DIFF/ IF(24),FF(24),STLFF(375)
 DIMENSION ARRAYX(27,27), ARRAYY(27,27)
 *, ITR(2), GRID(24,24), GRIDJ(24,24)
 CHARACTER*8 ITR(2),IT,IN,IF,LABEL(2),ITR
 DATA IF(1) /DIFFER 24/
 *, ITR(1) /HRRR+ 24/
 *, ITR(2)/24 542/
 *, IF(2)/24 542/
 *, ITR(4) /R4F04400.IY/
 *, IF(4) /R4F04400.JY/
 CALL R4INASC(ITAU,IT)
 ITR(2) = ITR(1)
 K = 0
 NVX = NX - 1
 NVY = NY - 1
 DO 100 I = 2,NVX
 DO 100 J = 2,NVY
 K = K + 1
 II = I + 1
 JJ = J + 1
 X = GRID(II,JJ) - 31.0
 Y = GRID(II,JJ) - 31.0

00007
 00008
 00009
 00010
 00011
 00012
 00013
 00014
 00015
 00016
 00017
 00018

000

CALL HVDIFF(U,V,GRID,FF,X,Y) IS USED TO CONVERT GRID
 ORIENTED WIND COMPONENTS(U,V) ON POLAR STEREOGRAPHIC
 GRID TO DIRECTION (DD) AND MAGNITUDE (FF) AND THE

```

RTMAN 1.5.1 CYCLE FTN1534  R11LT 02/03/91 23 27  SOURCE LISTING
00001      SUBROUTINE STATRT(TSTOP)
00002      COMMON /TIME/ RELAXS,FORMS,ADVCTS,GRXTHS,HEATS,MESHES,INITS
00003      PRINT 1
00004      1  FORMAT(11.1  TIME  STATISTICS)
00005      PRINT 10,TSTOP
00006      10  FORMAT(1X,TOTAL ICE MODEL TIME          1.F10.4)
00007      PRINT 20,RELAXS
00008      20  FORMAT(1X,RELAXATION TIME . . . . . 1.F10.4)
00009      PRINT 30,FORMS
00010      30  FORMAT(1X,FORMS AND PLASTIC TIME . . 1.F10.4)
00011      PRINT 40,ADVCTS
00012      40  FORMAT(1X,ADVECTION TIME . . . . . 1.F10.4)
00013      PRINT 50,GRXTHS
00014      50  FORMAT(1X,GRXTH TIME . . . . . 1.F10.4)
00015      PRINT 60,HEATS
00016      60  FORMAT(1X,HEAT BUDGET TIME . . . . . 1.F10.4)
00017      PRINT 70,MESHES
00018      70  FORMAT(1X,INITIALIZING GRID AND OCEAN 1.F10.4)
00019      PRINT 80,INITS
00020      80  FORMAT(1X,READING GRID/DI TIME . . . 1.F10.4)
00021      RETURN
00022      END
NO FORMS

```

TRAN 1.5.1 CYCLE STN1334 BUILT 09/03/81 23 27 SOURCE LISTING

```

00001      SUBROUTINE PRNT(ARRAY,I,J,K,M1,M2,N)
      CCC
      C      SUBROUTINE PRNT
      C
      C      PURPOSE:      TO PRINT A MODEL ARRAY
      C
      C      USAGE
      C
      C      ARRAY      THE ARRAY TO BE PRINTED
      C      I,J,K      DIMENSIONS OF ARRAY
      C      M1,N      ROWS AND COLUMNS OF ARRAY TO BE PRINTED
      C
      CCC
00002      DIMENSION ARRAY(I,J,K)
00003      PRINT *
00004      PRINT 7,M1,M2
00005      7      FORMAT(1X,1J FROM 1.13.1 TO 1.13)
00006      DO 10 KK = 1,I
00007      DO 10 JJ = 1,J
00008      PRINT 20,(ARRAY(I1,JJ,KK),JJ=M1,M2)
00009      10      CONTINUE
00010      PRINT *
00011      5      FORMAT(///)
00012      20      FORMAT(1X,13F2.3)
00013      RETURN
00014      END
      NO FORG-5

```

```
00022      IDA(1) = 100
00023      LABEL(1) = IDA(1)
00024      LABEL(2) = IDA(2)
00025      CALL SUBITER(ITERF,LABEL,IDA,649,ISTAT)
00026      IF(ISTAT.NE.0) GO TO 1000
```

```
00027      C O M P A C T N E S S
00028      C
```

```
00027      K = 0
00028      DO 20 I = 2,NMXX
00029      DO 20 J = 2,NMYY
00030      K = K + 1
00031      AXPAY(K) = AREA(I,J)
00032      CONTINUE
00033      IDA(1) = 101
00034      LABEL(1) = IDA(1)
00035      CALL SUBITER(ITERF,LABEL,IDA,649,ISTAT)
00036      IF(ISTAT.NE.0) GO TO 1000
```

```
00037      ICF DESCRIBE
```

```
00037      K = 0
00038      DO 30 I = 2,NMXX
00039      DO 30 J = 2,NMYY
00040      K = K + 1
00041      AXPAY(K) = DWEISS(J)
00042      CONTINUE
00043      IDA(1) = 102
00044      LABEL(1) = IDA(1)
00045      CALL SUBITER(ITERF,LABEL,IDA,649,ISTAT)
00046      IF(ISTAT.NE.0) GO TO 1000
```

```
00047      RETURN
00048 1000 PRINT 1010,ISTAT,LABEL
00049 1010 FORMAT(100,10)WRITE STATUS IS 1.15.1 10 WRITE OF 1.214)
00050      STOP WRITE TO HAPLOT
00051      END
```

END FORTRAN


```

C SIMPLIFIED FORMULA:
00051 121 G12=X12+Y12+X12-X13-X13
00052 GJ3 = YJ3 - YJ2
00053 GJ4 = YJ3 - YJ2 + GJ3
00054 GJ2 = YJ2 - GJ3 - GJ3
00055 GJ1 = 1.0 - GJ2
00056 PHI = (G4*GJ1)+G4*GJ2+((P11-P4)*GJ3+(P2-P1)*GJ4)*0.5*(1.-G12)
+ ((P3*GJ1)+P3*GJ2+((P12-P5)*GJ3+(P9-P2)*GJ4)*0.5)*G12
+ 0.5*((P4-P4)*GJ1+(P10-P4)*GJ2)*(X13-X12)
+ ((P3-P3)*GJ1+(P9-P7)*GJ2)*(X1-X12-X12+X13) )
00057 RETURN

C
C
C SPECIAL CASES:
C
C SPECIAL CASE 1: YJ=0
00059 51 P3=7(L+1)
00060 IF (I.NF.1) GO TO 61
00061 P3 = P4 + P4 - P5
00062 GO TO 62
00063 61 P3=7(L-1)
00064 IF (I.NF.(N-1)) GO TO 63
00065 P4 = P5 + P5 - P4
00066 GO TO 64
00067 63 P4 = 7(L + 2)
00068 GO TO 64

C
C SPECIAL CASE 2: X1=0
00069 52 P5 = 7(L + M)
00070 X1 = YJ
00071 IF (J.NF.1) GO TO 61
00072 P3 = P4 + P4 - P5
00073 GO TO 62
00074 61 P3=7(L-M)
00075 IF (J.NF.(N-1)) GO TO 63
00076 P6 = P5 + P5 - P4
00077 GO TO 64
00078 63 P6 = 7(L+M+M)

C
C SPECIAL FORMULA:
00079 64 X12 = X1 * X1
00080 X13 = X12 * X1
00081 G12=X12-G13-G13
00082 G14=X1-Y12+G13
00083 PHI=(1.-G12)*G4+G12*P5+(G13*(P4-P4)+G14*(P5-P3))*0.5
00084 RETURN

C
C
C SPECIAL CASE 3: X1=YJ=0
00085 53 PHI=P4
00086 RETURN

C
C
C PRINT Z(X,Y) OUT OF BOUNDS:
00087 99 PHI=MARK(53)
00088 RETURN

C
00089 END
V7 F33765

```

```

OUTPLAN 1.5.1 CYCLE FINISSE BUILT 09/03/81 23 27 SOURCE LISTING
00001 SUBROUTINE GROWDEC(HDIFF,FHEFF,GARFA,IOTG,ITAJ,NX,NY)
00002 DIMENSION HDIFF(24,24), FHEFF(24,24), GARFA(24,24)
00003 COMMON /MV/ MV(24), DIVG(625), FILLV(375)
00004 CHARACTER*84 MV, LABEL(2), IOTG(3), ID, IOI
00005 CHARACTER*8 ITH
00006 DATA MV(3) /44 649/
00007 * IOT /44HDE+ 24/
00008 * IOT /44F4F+ 24/
00009 * IOT /44G4G+ 24/
00010 * MV(4) /44F25400HY/
00011 MV(2) = IOTG(1)
00012 IFILE = 744555VAC
00013
00014 C
00015 C OUTPUT THE OPEN WATER GROWTH
00016 C
00017 K = 0
00018 NVX = NVI = 1
00019 NVY = NVI = 1
00020 DO 10 I = 2,NVX
00021 DO 10 J = 2,NVY
00022 K = K + 1
00023 DIVG(K) = HDIFF(I,J)
00024 CONTINUE
00025 MV(1) = IOT
00026 LABEL(1) = MV(1)
00027 LABEL(2) = MV(2)
00028 CALL CWRTPE(IFILE,LABEL,MV,649,ISTAT)
00029 IF(ISTAT.NE.0) GO TO 1000
00030
00031 C
00032 C OUTPUT THE SH TERM OF THE THERMO. CONTINUITY EQUATION
00033 C
00034 K = 0
00035 DO 20 I = 2,NVX
00036 DO 20 J = 2,NVY
00037 K = K + 1
00038 DIVG(K) = FHEFF(I,J)
00039 CONTINUE
00040 LABEL(1) = IO
00041 MV(1) = IO
00042 CALL CWRTPE(IFILE,LABEL,MV,649,ISTAT)
00043 IF(ISTAT.NE.0) GO TO 1000
00044
00045 C
00046 C OUTPUT THE SA TERM OF THE THERMO CONTINUITY EQUATION
00047 C
00048 K = 0
00049 DO 30 I = 2,NVX
00050 DO 30 J = 2,NVY
00051 K = K + 1
00052 DIVG(K) = GARFA(I,J)
00053 CONTINUE
00054 LABEL(1) = IOI
00055 MV(1) = IOI
00056 CALL CWRTPE(IFILE,LABEL,MV,649,ISTAT)
00057 IF(ISTAT.NE.0) GO TO 1000
00058 RETURN
00059 1000 PRINT 1010,ISTAT,LABEL
00060 1010 FORMAT(140,'WRITE STATUS IS ',I5,' ON WRITE OF ',245)
00061 STOP READ WRITE IN GROWDEC
00062 EN

```

NO ERRORS

FORTRAN 1.5.1 CYCLE FTN1534 PRINT 09/03/81 23 27 SOURCE LISTING

```

00001 SUBROUTINE RUOYI(RUCED,VICED,GRDI,GRDJ,NX,NY)
00002 COMMON /STEP/ DELTAT,DELTAX,DELTAY,DELTA1,DELTA
00003 COMMON /RUOY/ RUOYI(20),RUOYJ(20),RX(20),RY(20)
00004 DIMENSION RUCED(27,27), VICED(27,27), GRDI(24,24), GRDJ(27,27)
00005 PRINT 100
00006 DO 50 L = 1,20
00007 IF(RX(L) .LT. 1) GO TO 1000
00008 IF(RX(L) .GT. NX) GO TO 1000
00009 IF(RY(L) .LT. 1) GO TO 1000
00010 IF(RY(L) .GT. NY) GO TO 1000
00011 CALL INTDP(RUCED,NX,NY,RX(L),RY(L),U)
00012 CALL INTDP(VICED,NX,NY,RX(L),RY(L),V)
00013 U = (U * 86400.0) / DELTAY
00014 V = (V * 86400.0) / DELTAY
00015 SPACEI = U * DELTA
00016 SPACEJ = V * DELTA1
00017 RUOYI(L) = RUOYI(L) + SPACEI
00018 RUOYJ(L) = RUOYJ(L) + SPACEJ
00019 RX(L) = RX(L) + U
00020 RY(L) = RY(L) + V
00021 PRINT 105
00022 PRINT 105,L,RX(L),RY(L),RUOYI(L),RUOYJ(L)
00023 105 FORMAT(1X,I5,4F10.4)
00024 100 FORMAT(140,1RUOY NO. 1.1 X 1.1 Y 1.1 I 1.1
00025 * 1.1 J 1.1)
00025 1000 CONTINUE
00026 50 CONTINUE
00027 RETURN
00028 END

```

NO ERROR

REPORT DOCUMENTATION PAGE		READ INSTRUCTIONS BEFORE COMPLETING FORM
1. REPORT NUMBER NORDA Tech Note 122	2. GOVT ACCESSION NO. AD-A114 343	3. RECIPIENT'S CATALOG NUMBER
4. TITLE (and Subtitle) Program Maintenance Manual Polar Ice Forecast Subsystem - Arctic		5. TYPE OF REPORT & PERIOD COVERED Preliminary FY81
		6. PERFORMING ORG. REPORT NUMBER
7. AUTHOR(s) P. A. Harr, T. C. Pham and J. P. Welsh		8. CONTRACT OR GRANT NUMBER(s) N0014-81-F-0028
9. PERFORMING ORGANIZATION NAME AND ADDRESS Control Data Corporation 205 Montecito Ave. Monterey, CA 93940		10. PROGRAM ELEMENT, PROJECT, TASK AREA & WORK UNIT NUMBERS 93321D work unit
11. CONTROLLING OFFICE NAME AND ADDRESS Naval Air System Command Jefferson Davis Highway Arlington, VA 22210		12. REPORT DATE October 1981
		13. NUMBER OF PAGES 146
14. MONITORING AGENCY NAME & ADDRESS (if different from Controlling Office) Polar Oceanography Branch NORDA NSTL Station, MS 39529		15. SECURITY CLASS. (of this report) UNCLASSIFIED
		15a. DECLASSIFICATION/DOWNGRADING SCHEDULE None
16. DISTRIBUTION STATEMENT (of this Report) Unlimited		
17. DISTRIBUTION STATEMENT (of the abstract entered in Block 20, if different from Report) Unlimited		
18. SUPPLEMENTARY NOTES		
19. KEY WORDS (Continue on reverse side if necessary and identify by block number) Numerical model Sea Ice Polar Arctic Ice Forecasting Program maintenance		
20. ABSTRACT (Continue on reverse side if necessary and identify by block number) This manual provides a complete and detailed description of the dynamic thermodynamic sea ice model (PIFS-N) including all the necessary information for maintenance programmer personnel required to maintain the system.		

